

n."

## **A Consumer Library Interface to DWARF**

*David Anderson*

### **1. INTRODUCTION**

This document describes an interface to *libdwarf*, a library of functions to provide access to DWARF debugging information records, DWARF line number information, DWARF address range and global names information, weak names information, DWARF frame description information, DWARF static function names, DWARF static variables, and DWARF type information.

The document has long mentioned the "Unix International Programming Languages Special Interest Group" (PLSIG), under whose auspices the DWARF committee was formed around 1991. "Unix International" was disbanded in the 1990s and no longer exists.

The DWARF committee published DWARF2 July 27, 1993.

In the mid 1990s this document and the library it describes (which the committee never endorsed, having decided not to endorse or approve any particular library interface) was made available on the internet by Silicon Graphics, Inc.

In 2005 the DWARF committee began an affiliation with FreeStandards.org. In 2007 FreeStandards.org merged with The Linux Foundation. The DWARF committee dropped its affiliation with FreeStandards.org in 2007 and established the dwarfstd.org website. See "<http://www.dwarfstd.org>" for current information on standardization activities and a copy of the standard.

#### **1.1 Copyright**

Copyright 1993-2006 Silicon Graphics, Inc.

Copyright 2007-2013 David Anderson.

Permission is hereby granted to copy or republish or use any or all of this document without restriction except that when publishing more than a small amount of the document please acknowledge Silicon Graphics, Inc and David Anderson.

This document is distributed in the hope that it would be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

#### **1.2 Purpose and Scope**

The purpose of this document is to document a library of functions to access DWARF debugging information. There is no effort made in this document to address the creation of these records as those issues are addressed separately (see "A Producer Library Interface to DWARF").

Additionally, the focus of this document is the functional interface, and as such, implementation as well as optimization issues are intentionally ignored.

#### **1.3 Document History**

A document was written about 1991 which had similar layout and interfaces. Written by people from Hal

Corporation, That document described a library for reading DWARF1. The authors distributed paper copies to the committee with the clearly expressed intent to propose the document as a supported interface definition. The committee decided not to pursue a library definition.

SGI wrote the document you are now reading in 1993 with a similar layout and content and organization, but it was complete document rewrite with the intent to read DWARF2 (the DWARF version then in existence). The intent was (and is) to also cover future revisions of DWARF. All the function interfaces were changed in 1994 to uniformly return a simple integer success-code (see DW\_DLV\_OK etc), generally following the recommendations in the chapter titled "Candy Machine Interfaces" of "Writing Solid Code", a book by Steve Maguire (published by Microsoft Press).

## 1.4 Definitions

DWARF debugging information entries (DIEs) are the segments of information placed in the `.debug_*` sections by compilers, assemblers, and linkage editors that, in conjunction with line number entries, are necessary for symbolic source-level debugging. Refer to the latest "*DWARF Debugging Information Format*" from [www.dwarfstd.org](http://www.dwarfstd.org) for a more complete description of these entries.

This document adopts all the terms and definitions in "*DWARF Debugging Information Format*" versions 2,3, and 4. It originally focused on the implementation at Silicon Graphics, Inc., but now attempts to be more generally useful.

## 1.5 Overview

The remaining sections of this document describe the proposed interface to `libdwarf`, first by describing the purpose of additional types defined by the interface, followed by descriptions of the available operations. This document assumes you are thoroughly familiar with the information contained in the *DWARF Debugging Information Format* document.

We separate the functions into several categories to emphasize that not all consumers want to use all the functions. We call the categories Debugger, Internal-level, High-level, and Miscellaneous not because one is more important than another but as a way of making the rather large set of function calls easier to understand.

Unless otherwise specified, all functions and structures should be taken as being designed for Debugger consumers.

The Debugger Interface of this library is intended to be used by debuggers. The interface is low-level (close to dwarf) but suppresses irrelevant detail. A debugger will want to absorb all of some sections at startup and will want to see little or nothing of some sections except at need. And even then will probably want to absorb only the information in a single compilation unit at a time. A debugger does not care about implementation details of the library.

The Internal-level Interface is for a DWARF prettyprinter and checker. A thorough prettyprinter will want to know all kinds of internal things (like actual FORM numbers and actual offsets) so it can check for appropriate structure in the DWARF data and print (on request) all that internal information for human users and libdwarf authors and compiler-writers. Calls in this interface provide data a debugger does not care about.

The High-level Interface is for higher level access (it is not really a high level interface!). Programs such as disassemblers will want to be able to display relevant information about functions and line numbers without having to invest too much effort in looking at DWARF.

The miscellaneous interface is just what is left over: the error handler functions.

The following is a brief mention of the changes in this libdwarf from the libdwarf draft for DWARF Version 1 and recent changes.

## 1.6 Items Changed

Added a printf-callback so libdwarf will not actually print to stdout. Added dwarf\_highpc\_b() so return of a DWARF4 DW\_AT\_high\_pc of class constant can be returned properly. (August 15 2013)

Defined how the new operator DW\_OP\_GNU\_const\_type is handled. (January 26 2013)

Added dwarf\_loclist\_from\_expr\_b() function which adds arguments of the DWARF version (2 for DWARF2, etc) and the offset size to the dwarf\_loclist\_from\_expr\_a() function. Because the DW\_OP\_GNU\_implicit\_pointer opcode is defined differently for DWARF2 than for later versions. (November 2012)

Added new functions (some for libdwarf client code) and internal logic support for the DWARF4 .debug\_types section. The new functions are dwarf\_next\_cu\_header\_c(), dwarf\_siblingof\_b(), dwarf\_offdie\_b(), dwarf\_get\_cu\_die\_offset\_given\_cu\_header\_offset\_b(), dwarf\_get\_die\_infotypes\_flag(), dwarf\_get\_section\_max\_offsets\_b().

New functions and logic support additional detailed error reporting so that more compiler bugs can be reported sensibly by consumer code (as opposed to having libdwarf just assume things are ok and blindly continuing on with erroneous data). November 20, 2010

It seems impossible to default to both DW\_FRAME\_CFA\_COL and DW\_FRAME\_CFA\_COL3 in a single build of libdwarf, so the default is now unambiguously DW\_FRAME\_CFA\_COL3 unless the configure option --enable-oldframecol is specified at configure time. The function dwarf\_set\_frame\_cfa\_value() may be used to override the default : using that function gives consumer applications full control (its use is highly recommended). (January 17,2010)

Added dwarf\_set\_reloc\_application() and the default automatic application of Elf 'rela' relocations to DWARF sections (such rela sections appear in .o files, not in executables or shared objects, in general). The dwarf\_set\_reloc\_application() routine lets a consumer turn off the automatic application of 'rela' relocations if desired (it is not clear why anyone would really want to do that, but possibly a consumer could write its own relocation application). An example application that traverses a set of DIEs was added to the new dwarfexample directory (not in this libdwarf directory, but in parallel to it). (July 10, 2009)

Added dwarf\_get\_TAG\_name() (and the FORM AT and so on) interface functions so applications can get the string of the TAG, Attribute, etc as needed. (June 2009)

Added dwarf\_get\_ranges\_a() and dwarf\_loclist\_from\_expr\_a() functions which add arguments allowing a correct address\_size when the address\_size varies by compilation unit (a varying address\_size is quite rare as of May 2009). (May 2009)

Added dwarf\_set\_frame\_same\_value(), and dwarf\_set\_frame\_undefined\_value() to complete the set of frame-information functions needed to allow an application get all frame information returned correctly (meaning that it can be correctly interpreted) for all ABIs. Documented dwarf\_set\_frame\_cfa\_value(). Corrected spelling to dwarf\_set\_frame\_rule\_initial\_value(). (April 2009).

Added support for various DWARF3 features, but primarily a new frame-information interface tailorable at run-time to more than a single ABI. See dwarf\_set\_frame\_rule\_initial\_value(), dwarf\_set\_frame\_rule\_table\_size(), dwarf\_set\_frame\_cfa\_value(). See also dwarf\_get\_fde\_info\_for\_reg3() and dwarf\_get\_fde\_info\_for\_cfa\_reg3(). (April 2006)

Added support for DWARF3 .debug\_pubtypes section. Corrected various leaks (revising dealloc() calls, adding new functions) and corrected dwarf\_formstring() documentation.

Added dwarf\_srclines\_dealloc() as the previous deallocation method documented for data returned by dwarf\_srclines() was incapable of freeing all the allocated storage (14 July 2005).

dwarf\_nextglob(), dwarf\_globname(), and dwarf\_globdie() were all changed to operate on the items in the .debug\_pubnames section.

All functions were modified to return solely an error code. Data is returned through pointer arguments. This makes writing safe and correct library-using-code far easier. For justification for this approach, see

the chapter titled "Candy Machine Interfaces" in the book "Writing Solid Code" by Steve Maguire.

## 1.7 Items Removed

Dwarf\_Type was removed since types are no longer special.

dwarf\_typeof() was removed since types are no longer special.

Dwarf\_Ellist was removed since element lists no longer are a special format.

Dwarf\_Bounds was removed since bounds have been generalized.

dwarf\_nextdie() was replaced by dwarf\_next\_cu\_header() to reflect the real way DWARF is organized. The dwarf\_nextdie() was only useful for getting to compilation unit beginnings, so it does not seem harmful to remove it in favor of a more direct function.

dwarf\_childcnt() is removed on grounds that no good use was apparent.

dwarf\_prevline() and dwarf\_nextline() were removed on grounds this is better left to a debugger to do. Similarly, dwarf\_dieline() was removed.

dwarf\_is1stline() was removed as it was not meaningful for the revised DWARF line operations.

Any libdwarf implementation might well decide to support all the removed functionality and to retain the DWARF Version 1 meanings of that functionality. This would be difficult because the original libdwarf draft specification used traditional C library interfaces which confuse the values returned by successful calls with exceptional conditions like failures and 'no more data' indications.

## 1.8 Revision History

October 2011	DWARF4 support for reading .debug_types added.
March 93	Work on DWARF2 SGI draft begins
June 94	The function returns are changed to return an error/success code only.
April 2006:	Support for DWARF3 consumer operations is close to completion.
November 2010:	Added various new functions and improved error checking.

## 2. Types Definitions

### 2.1 General Description

The *libdwarf.h* header file contains typedefs and preprocessor definitions of types and symbolic names used to reference objects of *libdwarf*. The types defined by typedefs contained in *libdwarf.h* all use the convention of adding Dwarf\_ as a prefix and can be placed in three categories:

- Scalar types : The scalar types defined in *libdwarf.h* are defined primarily for notational convenience and identification. Depending on the individual definition, they are interpreted as a value, a pointer, or as a flag.
- Aggregate types : Some values can not be represented by a single scalar type; they must be represented by a collection of, or as a union of, scalar and/or aggregate types.
- Opaque types : The complete definition of these types is intentionally omitted; their use is as handles for query operations, which will yield either an instance of another opaque type to be used in another query, or an instance of a scalar or aggregate type, which is the actual result.

## 2.2 Scalar Types

The following are the defined by *libdwarf.h*:

```
typedef int Dwarf_Bool;
typedef unsigned long long Dwarf_Off;
typedef unsigned long long Dwarf_Unsigned;
typedef unsigned short Dwarf_Half;
typedef unsigned char Dwarf_Small;
typedef signed long long Dwarf_Signed;
typedef unsigned long long Dwarf_Addr;
typedef void *Dwarf_Ptr;
typedef void (*Dwarf_Handler)(Dwarf_Error *error, Dwarf_Ptr errarg);
```

Dwarf\_Ptr is an address for use by the host program calling the library, not for representing pc-values/addresses within the target object file. Dwarf\_Addr is for pc-values within the target object file. The sample scalar type assignments above are for a *libdwarf.h* that can read and write 32-bit or 64-bit binaries on a 32-bit or 64-bit host machine. The types must be defined appropriately for each implementation of libdwarf. A description of these scalar types in the SGI/MIPS environment is given in Figure 1.

NAME	SIZE	ALIGNMENT	PURPOSE
Dwarf_Bool	4	4	Boolean states
Dwarf_Off	8	8	Unsigned file offset
Dwarf_Unsigned	8	8	Unsigned large integer
Dwarf_Half	2	2	Unsigned medium integer
Dwarf_Small	1	1	Unsigned small integer
Dwarf_Signed	8	8	Signed large integer
Dwarf_Addr	8	8	Program address (target program)
Dwarf_Ptr	4 8	4 8	Dwarf section pointer (host program)
Dwarf_Handler	4 8	4 8	Pointer to error handler function

**Figure 1.** Scalar Types

## 2.3 Aggregate Types

The following aggregate types are defined by *libdwarf.h*: Dwarf\_Loc, Dwarf\_Locdesc, Dwarf\_Block, Dwarf\_Frame\_Op, Dwarf\_Regtable, Dwarf\_Regtable3. While most of libdwarf acts on or returns simple values or opaque pointer types, this small set of structures seems useful.

### 2.3.1 Location Record

The Dwarf\_Loc type identifies a single atom of a location description or a location expression.

```
typedef struct {
    Dwarf_Small      lr_atom;
    Dwarf_Unsigned   lr_number;
    Dwarf_Unsigned   lr_number2;
    Dwarf_Unsigned   lr_offset;
} Dwarf_Loc;
```

The `lr_atom` identifies the atom corresponding to the `DW_OP_*` definition in *dwarf.h* and it represents the operation to be performed in order to locate the item in question.

The `lr_number` field is the operand to be used in the calculation specified by the `lr_atom` field; not all atoms use this field. Some atom operations imply signed numbers so it is necessary to cast this to a `Dwarf_Signed` type for those operations.

The `lr_number2` field is the second operand specified by the `lr_atom` field; only `DW_OP_BREGX` has this field. Some atom operations imply signed numbers so it may be necessary to cast this to a `Dwarf_Signed` type for those operations.

For a `DW_OP_implicit_value` operator the `lr_number2` field is a pointer to the bytes of the value. The field pointed to is `lr_number` bytes long. There is no explicit terminator. Do not attempt to *free* the bytes which `lr_number2` points at and do not alter those bytes. The pointer value remains valid till the open `Dwarf_Debug` is closed. This is a rather ugly use of a host integer to hold a pointer. You will normally have to do a 'cast' operation to use the value.

For a `DW_OP_GNU_const_type` operator the `lr_number2` field is a pointer to a block with an initial unsigned byte giving the number of bytes following, followed immediately that number of const value bytes. There is no explicit terminator. Do not attempt to *free* the bytes which `lr_number2` points at and do not alter those bytes. The pointer value remains valid till the open `Dwarf_Debug` is closed. This is a rather ugly use of a host integer to hold a pointer. You will normally have to do a 'cast' operation to use the value.

The `lr_offset` field is the byte offset (within the block the location record came from) of the atom specified by the `lr_atom` field. This is set on all atoms. This is useful for operations `DW_OP_SKIP` and `DW_OP_BRA`.

### 2.3.2 Location Description

The `Dwarf_Locdesc` type represents an ordered list of `Dwarf_Loc` records used in the calculation to locate an item. Note that in many cases, the location can only be calculated at runtime of the associated program.

```
typedef struct {
    Dwarf_Addr      ld_lopc;
    Dwarf_Addr      ld_hipc;
    Dwarf_Unsigned   ld_cents;
    Dwarf_Loc*      ld_s;
} Dwarf_Locdesc;
```

The `ld_lopc` and `ld_hipc` fields provide an address range for which this location descriptor is valid. Both of these fields are set to *zero* if the location descriptor is valid throughout the scope of the item it is associated with. These addresses are virtual memory addresses, not offsets-from-something. The virtual memory addresses do not account for dso movement (none of the pc values from libdwarf do that, it is up to the consumer to do that).

The `ld_cents` field contains a count of the number of `Dwarf_Loc` entries pointed to by the `ld_s` field.

The `ld_s` field points to an array of `Dwarf_Loc` records.

### 2.3.3 Data Block

The `Dwarf_Block` type is used to contain the value of an attribute whose form is either `DW_FORM_block1`, `DW_FORM_block2`, `DW_FORM_block4`, `DW_FORM_block8`, or `DW_FORM_block`. Its intended use is to deliver the value for an attribute of any of these forms.

```
typedef struct {
    Dwarf_Unsigned    bl_len;
    Dwarf_Ptr         bl_data;
} Dwarf_Block;
```

The `bl_len` field contains the length in bytes of the data pointed to by the `bl_data` field.

The `bl_data` field contains a pointer to the uninterpreted data. Since we use a `Dwarf_Ptr` here one must copy the pointer to some other type (typically an `unsigned char *`) so one can add increments to index through the data. The data pointed to by `bl_data` is not necessarily at any useful alignment.

### 2.3.4 Frame Operation Codes: DWARF 2

This interface is adequate for DWARF2 but not for DWARF3. A separate interface usable for DWARF3 and for DWARF2 is described below. This interface is deprecated. Use the interface for DWARF3 and DWARF2. See also the section "Low Level Frame Operations" below.

The DWARF2 `Dwarf_Frame_Op` type is used to contain the data of a single instruction of an instruction-sequence of low-level information from the section containing frame information. This is ordinarily used by Internal-level Consumers trying to print everything in detail.

```
typedef struct {
    Dwarf_Small    fp_base_op;
    Dwarf_Small    fp_extended_op;
    Dwarf_Half     fp_register;
    Dwarf_Signed   fp_offset;
    Dwarf_Offset   fp_instr_offset;
} Dwarf_Frame_Op;
```

`fp_base_op` is the 2-bit basic op code. `fp_extended_op` is the 6-bit extended opcode (if `fp_base_op` indicated there was an extended op code) and is zero otherwise.

`fp_register` is any (or the first) register value as defined in the Call Frame Instruction Encodings figure in the dwarf document. If not used with the Op it is 0.

`fp_offset` is the address, delta, offset, or second register as defined in the Call Frame Instruction Encodings figure in the dwarf document. If this is an address then the value should be cast to (`Dwarf_Addr`) before being used. In any implementation this field *must* be as large as the larger of `Dwarf_Signed` and `Dwarf_Addr` for this to work properly. If not used with the op it is 0.

`fp_instr_offset` is the `byte_offset` (within the instruction stream of the frame instructions) of this operation. It starts at 0 for a given frame descriptor.

### 2.3.5 Frame Regtable: DWARF 2

This interface is adequate for DWARF2 and MIPS but not for DWARF3. A separate and preferred interface usable for DWARF3 and for DWARF2 is described below. See also the section "Low Level Frame Operations" below.

The Dwarf\_Regtable type is used to contain the register-restore information for all registers at a given PC value. Normally used by debuggers. If you wish to default to this interface and to the use of DW\_FRAME\_CFA\_COL, specify --enable\_oldframecol at libdwarf configure time. Or add a call dwarf\_set\_frame\_cfa\_value(dbg,DW\_FRAME\_CFA\_COL) after your dwarf\_init() call, this call replaces the default libdwarf-compile-time value with DW\_FRAME\_CFA\_COL.

```
/* DW_REG_TABLE_SIZE must reflect the number of registers
*(DW_FRAME_LAST_REG_NUM) as defined in dwarf.h
*/
#define DW_REG_TABLE_SIZE <fill in size here, 66 for MIPS/IRIX>
typedef struct {
    struct {
        Dwarf_Small      dw_offset_relevant;
        Dwarf_Half       dw_regnum;
        Dwarf_Addr        dw_offset;
    }
    rules[DW_REG_TABLE_SIZE];
} Dwarf_Regtable;
```

The array is indexed by register number. The field values for each index are described next. For clarity we describe the field values for index rules[M] (M being any legal array element index).

dw\_offset\_relevant is non-zero to indicate the dw\_offset field is meaningful. If zero then the dw\_offset is zero and should be ignored.

dw\_regnum is the register number applicable. If dw\_offset\_relevant is zero, then this is the register number of the register containing the value for register M. If dw\_offset\_relevant is non-zero, then this is the register number of the register to use as a base (M may be DW\_FRAME\_CFA\_COL, for example) and the dw\_offset value applies. The value of register M is therefore the value of register dw\_regnum.

dw\_offset should be ignored if dw\_offset\_relevant is zero. If dw\_offset\_relevant is non-zero, then the consumer code should add the value to the value of the register dw\_regnum to produce the value.

### 2.3.6 Frame Operation Codes: DWARF 3 (and DWARF2)

This interface is adequate for DWARF3 and for DWARF2 (and DWARF4). It is new in libdwarf in April 2006. See also the section "Low Level Frame Operations" below.

The DWARF2 Dwarf\_Frame\_Op3 type is used to contain the data of a single instruction of an instruction-sequence of low-level information from the section containing frame information. This is ordinarily used by Internal-level Consumers trying to print everything in detail.



```
typedef struct {
    Dwarf_Small    fp_base_op;
    Dwarf_Small    fp_extended_op;
    Dwarf_Half     fp_register;

    /* Value may be signed, depends on op.
       Any applicable data_alignment_factor has
       not been applied, this is the raw offset. */
    Dwarf_Unsigned fp_offset_or_block_len;
    Dwarf_Small    *fp_expr_block;

    Dwarf_Off      fp_instr_offset;
} Dwarf_Frame_Op3;
```

`fp_base_op` is the 2-bit basic op code. `fp_extended_op` is the 6-bit extended opcode (if `fp_base_op` indicated there was an extended op code) and is zero otherwise.

`fp_register` is any (or the first) register value as defined in the Call Frame Instruction Encodings figure in the dwarf document. If not used with the Op it is 0.

`fp_offset_or_block_len` is the address, delta, offset, or second register as defined in the Call Frame Instruction Encodings figure in the dwarf document. Or (depending on the op, it may be the length of the dwarf-expression block pointed to by `fp_expr_block`. If this is an address then the value should be cast to (`Dwarf_Addr`) before being used. In any implementation this field *must* be as large as the larger of `Dwarf_Signed` and `Dwarf_Addr` for this to work properly. If not used with the op it is 0.

`fp_expr_block` (if applicable to the op) points to a dwarf-expression block which is `fp_offset_or_block_len` bytes long.

`fp_instr_offset` is the `byte_offset` (within the instruction stream of the frame instructions) of this operation. It starts at 0 for a given frame descriptor.

### 2.3.7 Frame Regtable: DWARF 3

This interface is adequate for DWARF3 and for DWARF2. It is new in libdwarf as of April 2006. The default configure of libdwarf inserts `DW_FRAME_CFA_COL3` as the default CFA column. Or add a call `dwarf_set_frame_cfa_value(dbg,DW_FRAME_CFA_COL3)` after your `dwarf_init()` call, this call replaces the default libdwarf-compile-time value with `DW_FRAME_CFA_COL3`.

The `Dwarf_Regtable3` type is used to contain the register-restore information for all registers at a given PC value. Normally used by debuggers.

```
typedef struct Dwarf_Regtable_Entry3_s {
    Dwarf_Small      dw_offset_relevant;
    Dwarf_Small      dw_value_type;
    Dwarf_Half       dw_regnum;
    Dwarf_Unsigned   dw_offset_or_block_len;
    Dwarf_Ptr        dw_block_ptr;
} Dwarf_Regtable_Entry3;

typedef struct Dwarf_Regtable3_s {
    struct Dwarf_Regtable_Entry3_s    rt3_cfa_rule;

    Dwarf_Half                        rt3_reg_table_size;
    struct Dwarf_Regtable_Entry3_s * rt3_rules;
} Dwarf_Regtable3;
```

The array is indexed by register number. The field values for each index are described next. For clarity we describe the field values for index rules[M] (M being any legal array element index). (DW\_FRAME\_CFA\_COL3, DW\_FRAME\_SAME\_VAL, DW\_FRAME\_UNDEFINED\_VAL are not legal array indexes, nor is any index < 0 or >= rt3\_reg\_table\_size); The caller of routines using this struct must create data space for rt3\_reg\_table\_size entries of struct Dwarf\_Regtable\_Entry3\_s and arrange that rt3\_rules points to that space and that rt3\_reg\_table\_size is set correctly. The caller need not (but may) initialize the contents of the rt3\_cfa\_rule or the rt3\_rules array. The following applies to each rt3\_rules rule M:

dw\_regnum is the register number applicable. If dw\_regnum is DW\_FRAME\_UNDEFINED\_VAL, then the register I has undefined value. If dw\_regnum is DW\_FRAME\_SAME\_VAL, then the register I has the same value as in the previous frame.

If dw\_regnum is neither of these two, then the following apply:

dw\_value\_type determines the meaning of the other fields. It is one of DW\_EXPR\_OFFSET (0), DW\_EXPR\_VAL\_OFFSET(1), DW\_EXPR\_EXPRESSION(2) or DW\_EXPR\_VAL\_EXPRESSION(3).

If dw\_value\_type is DW\_EXPR\_OFFSET (0) then this is as in DWARF2 and the offset(N) rule or the register(R) rule of the DWARF3 and DWARF2 document applies. The value is either:

If dw\_offset\_relevant is non-zero, then dw\_regnum is effectively ignored but must be identical to DW\_FRAME\_CFA\_COL3 (and the dw\_offset value applies. The value of register M is therefore the value of CFA plus the value of dw\_offset. The result of the calculation is the address in memory where the value of register M resides. This is the offset(N) rule of the DWARF2 and DWARF3 documents.

dw\_offset\_relevant is zero it indicates the dw\_offset field is not meaningful. The value of register M is the value currently in register dw\_regnum (the value DW\_FRAME\_CFA\_COL3 must not appear, only real registers). This is the register(R) rule of the DWARF3 spec.

If dw\_value\_type is DW\_EXPR\_OFFSET (1) then this is the the val\_offset(N) rule of the DWARF3 spec applies. The calculation is identical to that of DW\_EXPR\_OFFSET (0) but the value is interpreted as the value of register M (rather than the address where register M's value is stored).

If dw\_value\_type is DW\_EXPR\_EXPRESSION (2) then this is the the expression(E) rule of the DWARF3 document.

dw\_offset\_or\_block\_len is the length in bytes of the in-memory block pointed

at by `dw_block_ptr`. `dw_block_ptr` is a DWARF expression. Evaluate that expression and the result is the address where the previous value of register M is found.

If `dw_value_type` is `DW_EXPR_VAL_EXPRESSION` (3) then this is the `val_expression(E)` rule of the DWARF3 spec.

`dw_offset_or_block_len` is the length in bytes of the in-memory block pointed at by `dw_block_ptr`. `dw_block_ptr` is a DWARF expression. Evaluate that expression and the result is the previous value of register M.

The rule `rt3_cfa_rule` is the current value of the CFA. It is interpreted exactly like any register M rule (as described just above) except that `dw_regnum` cannot be `CW_FRAME_CFA_REG3` or `DW_FRAME_UNDEFINED_VAL` or `DW_FRAME_SAME_VAL` but must be a real register number.

## 2.3.8 Macro Details Record

The `Dwarf_Macro_Details` type gives information about a single entry in the `.debug.macro` section.

```
struct Dwarf_Macro_Details_s {
    Dwarf_Off    dmd_offset;
    Dwarf_Small  dmd_type;
    Dwarf_Signed dmd_lineno;
    Dwarf_Signed dmd_fileindex;
    char *       dmd_macro;
};
typedef struct Dwarf_Macro_Details_s Dwarf_Macro_Details;
```

`dmd_offset` is the byte offset, within the `.debug.macro` section, of this macro information.

`dmd_type` is the type code of this macro info entry (or 0, the type code indicating that this is the end of macro information entries for a compilation unit. See `DW_MACINFO_define`, etc in the DWARF document.

`dmd_lineno` is the line number where this entry was found, or 0 if there is no applicable line number.

`dmd_fileindex` is the file index of the file involved. This is only guaranteed meaningful on a `DW_MACINFO_start_file` `dmd_type`. Set to -1 if unknown (see the functional interface for more details).

`dmd_macro` is the applicable string. For a `DW_MACINFO_define` this is the macro name and value. For a `DW_MACINFO_undef`, or this is the macro name. For a `DW_MACINFO_vendor_ext` this is the vendor-defined string value. For other `dmd_types` this is 0.

## 2.4 Opaque Types

The opaque types declared in *libdwarf.h* are used as descriptors for queries against DWARF information stored in various debugging sections. Each time an instance of an opaque type is returned as a result of a *libdwarf* operation (`Dwarf_Debug` excepted), it should be freed, using `dwarf_dealloc()` when it is no longer of use (read the following documentation for details, as in at least one case there is a special routine provided for deallocation and `dwarf_dealloc()` is not directly called: see `dwarf_srclines()`). Some functions return a number of instances of an opaque type in a block, by means of a pointer to the block and a count of the number of opaque descriptors in the block: see the function description for deallocation rules for such functions. The list of opaque types defined in *libdwarf.h* that are pertinent to the Consumer Library, and their intended use is described below.

```
typedef struct Dwarf_Debug_s* Dwarf_Debug;
```

An instance of the `Dwarf_Debug` type is created as a result of a successful call to `dwarf_init()`, or `dwarf_elf_init()`, and is used as a descriptor for subsequent access to most `libdwarf` functions on that object. The storage pointed to by this descriptor should be not be freed, using the `dwarf_dealloc()` function. Instead free it with `dwarf_finish()`.

```
typedef struct Dwarf_Die_s* Dwarf_Die;
```

An instance of a `Dwarf_Die` type is returned from a successful call to the `dwarf_siblingof()`, `dwarf_child`, or `dwarf_offdie_b()` function, and is used as a descriptor for queries about information related to that DIE. The storage pointed to by this descriptor should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_DIE` when no longer needed.

```
typedef struct Dwarf_Line_s* Dwarf_Line;
```

Instances of `Dwarf_Line` type are returned from a successful call to the `dwarf_srclines()` function, and are used as descriptors for queries about source lines. The storage pointed to by these descriptors should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_LINE` when no longer needed.

```
typedef struct Dwarf_Global_s* Dwarf_Global;
```

Instances of `Dwarf_Global` type are returned from a successful call to the `dwarf_get_globals()` function, and are used as descriptors for queries about global names (pubnames).

```
typedef struct Dwarf_Weak_s* Dwarf_Weak;
```

Instances of `Dwarf_Weak` type are returned from a successful call to the SGI-specific `dwarf_get_weakes()` function, and are used as descriptors for queries about weak names. The storage pointed to by these descriptors should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_WEAK_CONTEXT` (or `DW_DLA_WEAK`, an older name, supported for compatibility) when no longer needed.

```
typedef struct Dwarf_Func_s* Dwarf_Func;
```

Instances of `Dwarf_Func` type are returned from a successful call to the SGI-specific `dwarf_get_funcs()` function, and are used as descriptors for queries about static function names.

```
typedef struct Dwarf_Type_s* Dwarf_Type;
```

Instances of `Dwarf_Type` type are returned from a successful call to the SGI-specific `dwarf_get_types()` function, and are used as descriptors for queries about user defined types.

```
typedef struct Dwarf_Var_s* Dwarf_Var;
```

Instances of `Dwarf_Var` type are returned from a successful call to the SGI-specific `dwarf_get_vars()` function, and are used as descriptors for queries about static variables.

```
typedef struct Dwarf_Error_s* Dwarf_Error;
```

This descriptor points to a structure that provides detailed information about errors detected by `libdwarf`. Users typically provide a location for `libdwarf` to store this descriptor for the user to obtain more information about the error. The storage pointed to by this descriptor should be freed, using

`dwarf_dealloc()` with the allocation type `DW_DLA_ERROR` when no longer needed.

```
typedef struct Dwarf_Attribute_s* Dwarf_Attribute;
```

Instances of `Dwarf_Attribute` type are returned from a successful call to the `dwarf_attrlist()`, or `dwarf_attr()` functions, and are used as descriptors for queries about attribute values. The storage pointed to by this descriptor should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ATTR` when no longer needed.

```
typedef struct Dwarf_Abbrev_s* Dwarf_Abbrev;
```

An instance of a `Dwarf_Abbrev` type is returned from a successful call to `dwarf_get_abbrev()`, and is used as a descriptor for queries about abbreviations in the `.debug_abbrev` section. The storage pointed to by this descriptor should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ABBREV` when no longer needed.

```
typedef struct Dwarf_Fde_s* Dwarf_Fde;
```

Instances of `Dwarf_Fde` type are returned from a successful call to the `dwarf_get_fde_list()`, `dwarf_get_fde_for_die()`, or `dwarf_get_fde_at_pc()` functions, and are used as descriptors for queries about frames descriptors.

```
typedef struct Dwarf_Cie_s* Dwarf_Cie;
```

Instances of `Dwarf_Cie` type are returned from a successful call to the `dwarf_get_fde_list()` function, and are used as descriptors for queries about information that is common to several frames.

```
typedef struct Dwarf_Arange_s* Dwarf_Arange;
```

Instances of `Dwarf_Arange` type are returned from successful calls to the `dwarf_get_aranges()`, or `dwarf_get_arange()` functions, and are used as descriptors for queries about address ranges. The storage pointed to by this descriptor should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ARANGE` when no longer needed.

### 3. Error Handling

The method for detection and disposition of error conditions that arise during access of debugging information via *libdwarf* is consistent across all *libdwarf* functions that are capable of producing an error. This section describes the method used by *libdwarf* in notifying client programs of error conditions.

Most functions within *libdwarf* accept as an argument a pointer to a `Dwarf_Error` descriptor where a `Dwarf_Error` descriptor is stored if an error is detected by the function. Routines in the client program that provide this argument can query the `Dwarf_Error` descriptor to determine the nature of the error and perform appropriate processing.

A client program can also specify a function to be invoked upon detection of an error at the time the library is initialized (see `dwarf_init()`). When a *libdwarf* routine detects an error, this function is called with two arguments: a code indicating the nature of the error and a pointer provided by the client at initialization (again see `dwarf_init()`). This pointer argument can be used to relay information between the error handler and other routines of the client program. A client program can specify or change both the error handling function and the pointer argument after initialization using `dwarf_seterrhand()` and `dwarf_seterrarg()`.

In the case where *libdwarf* functions are not provided a pointer to a `Dwarf_Error` descriptor, and no error handling function was provided at initialization, *libdwarf* functions terminate execution by calling `abort(3C)`.

The following lists the processing steps taken upon detection of an error:

1. Check the `error` argument; if not a `NULL` pointer, allocate and initialize a `Dwarf_Error` descriptor with information describing the error, place this descriptor in the area pointed to by `error`, and return a value indicating an error condition.
2. If an `errhand` argument was provided to `dwarf_init()` at initialization, call `errhand()` passing it the error descriptor and the value of the `errarg` argument provided to `dwarf_init()`. If the error handling function returns, return a value indicating an error condition.
3. Terminate program execution by calling `abort(3C)`.

In all cases, it is clear from the value returned from a function that an error occurred in executing the function, since `DW_DLV_ERROR` is returned.

As can be seen from the above steps, the client program can provide an error handler at initialization, and still provide an error argument to *libdwarf* functions when it is not desired to have the error handler invoked.

If a *libdwarf* function is called with invalid arguments, the behavior is undefined. In particular, supplying a `NULL` pointer to a *libdwarf* function (except where explicitly permitted), or pointers to invalid addresses or uninitialized data causes undefined behavior; the return value in such cases is undefined, and the function may fail to invoke the caller supplied error handler or to return a meaningful error number. Implementations also may abort execution for such cases.

Some errors are so inconsequential that it does not warrant rejecting an object or returning an error. An example would be a frame length not being a multiple of an address-size (right now this is the only such inconsequential error). To make it possible for a client to report such errors the function `dwarf_get_harmless_error_list` returns strings with error text in them. This function may be ignored if client code does not want to bother with such error reporting. See `DW_DLE_DEBUG_FRAME_LENGTH_NOT_MULTIPLE` in the *libdwarf* source code.

### 3.1 Returned values in the functional interface

Values returned by *libdwarf* functions to indicate success and errors are enumerated in Figure 2. The `DW_DLV_NO_ENTRY` case is useful for functions need to indicate that while there was no data to return there was no error either. For example, `dwarf_siblingof()` may return `DW_DLV_NO_ENTRY` to indicate that that there was no sibling to return.

SYMBOLIC NAME	VALUE	MEANING
<code>DW_DLV_ERROR</code>	1	Error
<code>DW_DLV_OK</code>	0	Successful call
<code>DW_DLV_NO_ENTRY</code>	-1	No applicable value

**Figure 2.** Error Indications

Each function in the interface that returns a value returns one of the integers in the above figure.

If `DW_DLV_ERROR` is returned and a pointer to a `Dwarf_Error` pointer is passed to the function, then a `Dwarf_Error` handle is returned through the pointer. No other pointer value in the interface returns a value.

After the `Dwarf_Error` is no longer of interest, a `dwarf_dealloc(dbg,dw_err,DW_DLA_ERROR)` on the error pointer is appropriate to free any space used by the error information.

If `DW_DLV_NO_ENTRY` is returned no pointer value in the interface returns a value.

If `DW_DLV_OK` is returned, the `Dwarf_Error` pointer, if supplied, is not touched, but any other values to be returned through pointers are returned. In this case calls (depending on the exact function returning the error) to `dwarf_dealloc()` may be appropriate once the particular pointer returned is no longer of interest.

Pointers passed to allow values to be returned through them are uniformly the last pointers in each argument list.

All the interface functions are defined from the point of view of the writer-of-the-library (as is traditional for UN\*X library documentation), not from the point of view of the user of the library. The caller might code:

```
Dwarf_Line line;
Dwarf_Signed ret_loff;
Dwarf_Error err;
int retval = dwarf_linenoff(line,&ret_loff,&err);
```

for the function defined as

```
int dwarf_linenoff(Dwarf_Line line,Dwarf_Signed *return_linenoff,
    Dwarf_Error* err);
```

and this document refers to the function as returning the value through `*err` or `*return_linenoff` or uses the phrase "returns in the location pointed to by `err`". Sometimes other similar phrases are used.

## 4. Memory Management

Several of the functions that comprise *libdwarf* return pointers (opaque descriptors) to structures that have been dynamically allocated by the library. To aid in the management of dynamic memory, the function `dwarf_dealloc()` is provided to free storage allocated as a result of a call to a *libdwarf* function. This section describes the strategy that should be taken by a client program in managing dynamic storage.

### 4.1 Read-only Properties

All pointers (opaque descriptors) returned by or as a result of a *libdwarf Consumer Library* call should be assumed to point to read-only memory. The results are undefined for *libdwarf* clients that attempt to write to a region pointed to by a value returned by a *libdwarf Consumer Library* call.

### 4.2 Storage Deallocation

See the section "Returned values in the functional interface", above, for the general rules where calls to `dwarf_dealloc()` is appropriate.

In some cases the pointers returned by a *libdwarf* call are pointers to data which is not freeable. The library knows from the allocation type provided to it whether the space is freeable or not and will not free inappropriately when `dwarf_dealloc()` is called. So it is vital that `dwarf_dealloc()` be called with the proper allocation type.

For most storage allocated by *libdwarf*, the client can free the storage for reuse by calling `dwarf_dealloc()`, providing it with the `Dwarf_Debug` descriptor specifying the object for which the storage was allocated, a pointer to the area to be free-ed, and an identifier that specifies what the pointer points to (the allocation type). For example, to free a `Dwarf_Die` `die` belonging the the object

represented by `Dwarf_Debug dbg`, allocated by a call to `dwarf_siblingof()`, the call to `dwarf_dealloc()` would be:

```
dwarf_dealloc(dbg, die, DW_DLA_DIE);
```

To free storage allocated in the form of a list of pointers (opaque descriptors), each member of the list should be deallocated, followed by deallocation of the actual list itself. The following code fragment uses an invocation of `dwarf_attrlist()` as an example to illustrate a technique that can be used to free storage from any *libdwarf* routine that returns a list:

```
Dwarf_Unsigned atcnt;
Dwarf_Attribute *atlist;
int errv;

errv = dwarf_attrlist(somedie, &atlist, &atcnt, &error);
if (errv == DW_DLV_OK) {
    for (i = 0; i < atcnt; ++i) {
        /* use atlist[i] */
        dwarf_dealloc(dbg, atlist[i], DW_DLA_ATTR);
    }
    dwarf_dealloc(dbg, atlist, DW_DLA_LIST);
}
```

The `Dwarf_Debug` returned from `dwarf_init()` or `dwarf_elf_init()` cannot be freed using `dwarf_dealloc()`. The function `dwarf_finish()` will deallocate all dynamic storage associated with an instance of a `Dwarf_Debug` type. In particular, it will deallocate all dynamically allocated space associated with the `Dwarf_Debug` descriptor, and finally make the descriptor invalid.

An `Dwarf_Error` returned from `dwarf_init()` or `dwarf_elf_init()` in case of a failure cannot be freed using `dwarf_dealloc()`. The only way to free the `Dwarf_Error` from either of those calls is to use *free(3)* directly. Every `Dwarf_Error` must be freed by `dwarf_dealloc()` except those returned by `dwarf_init()` or `dwarf_elf_init()`.

The codes that identify the storage pointed to in calls to `dwarf_dealloc()` are described in figure 3.



IDENTIFIER	USED TO FREE
DW_DLA_STRING	char*
DW_DLA_LOC	Dwarf_Loc
DW_DLA_LOCDISC	Dwarf_Locdesc
DW_DLA_ELLIST	Dwarf_Ellist (not used)
DW_DLA_BOUNDS	Dwarf_Bounds (not used)
DW_DLA_BLOCK	Dwarf_Block
DW_DLA_DEBUG	Dwarf_Debug (do not use)
DW_DLA_DIE	Dwarf_Die
DW_DLA_LINE	Dwarf_Line
DW_DLA_ATTR	Dwarf_Attribute
DW_DLA_TYPE	Dwarf_Type (not used)
DW_DLA_SUBSCR	Dwarf_Subscr (not used)
DW_DLA_GLOBAL_CONTEXT	Dwarf_Global
DW_DLA_ERROR	Dwarf_Error
DW_DLA_LIST	a list of opaque descriptors
DW_DLA_LINEBUF	Dwarf_Line* (not used)
DW_DLA_ARANGE	Dwarf_Arange
DW_DLA_ABBREV	Dwarf_Abbrev
DW_DLA_FRAME_OP	Dwarf_Frame_Op
DW_DLA_CIE	Dwarf_Cie
DW_DLA_FDE	Dwarf_Fde
DW_DLA_LOC_BLOCK	Dwarf_Loc Block
DW_DLA_FRAME_BLOCK	Dwarf_Frame Block (not used)
DW_DLA_FUNC_CONTEXT	Dwarf_Func
DW_DLA_TYPENAME_CONTEXT	Dwarf_Type
DW_DLA_VAR_CONTEXT	Dwarf_Var
DW_DLA_WEAK_CONTEXT	Dwarf_Weak
DW_DLA_PUBTYPES_CONTEXT	Dwarf_Type

**Figure 3.** Allocation/Deallocation Identifiers

## 5. Functional Interface

This section describes the functions available in the *libdwarf* library. Each function description includes its definition, followed by one or more paragraph describing the function's operation.

The following sections describe these functions.

### 5.1 Initialization Operations

These functions are concerned with preparing an object file for subsequent access by the functions in *libdwarf* and with releasing allocated resources when access is complete.

#### 5.1.1 dwarf\_init()

```
int dwarf_init(  
    int fd,  
    Dwarf_Unsigned access,  
    Dwarf_Handler errhand,  
    Dwarf_Ptr errarg,  
    Dwarf_Debug * dbg,  
    Dwarf_Error *error)
```

When it returns DW\_DLV\_OK, the function `dwarf_init()` returns through `dbg` a `Dwarf_Debug` descriptor that represents a handle for accessing debugging records associated with the open file descriptor `fd`. DW\_DLV\_NO\_ENTRY is returned if the object does not contain DWARF debugging information. DW\_DLV\_ERROR is returned if an error occurred. The `access` argument indicates what access is allowed for the section. The DW\_DLC\_READ parameter is valid for read access (only read access is defined or discussed in this document). The `errhand` argument is a pointer to a function that will be invoked whenever an error is detected as a result of a *libdwarf* operation. The `errarg` argument is passed as an argument to the `errhand` function. The file descriptor associated with the `fd` argument must refer to an ordinary file (i.e. not a pipe, socket, device, /proc entry, etc.), be opened with the at least as much permission as specified by the `access` argument, and cannot be closed or used as an argument to any system calls by the client until after `dwarf_finish()` is called. The seek position of the file associated with `fd` is undefined upon return of `dwarf_init()`.

With SGI IRIX, by default it is allowed that the app `close()` `fd` immediately after calling `dwarf_init()`, but that is not a portable approach (that it works is an accidental side effect of the fact that SGI IRIX uses ELF\_C\_READ\_MMAP in its hidden internal call to `elf_begin()`). The portable approach is to consider that `fd` must be left open till after the corresponding `dwarf_finish()` call has returned.

Since `dwarf_init()` uses the same error handling processing as other *libdwarf* functions (see *Error Handling* above), client programs will generally supply an `error` parameter to bypass the default actions during initialization unless the default actions are appropriate.

### 5.1.2 dwarf\_elf\_init()

```
int dwarf_elf_init(  
    Elf * elf_file_pointer,  
    Dwarf_Unsigned access,  
    Dwarf_Handler errhand,  
    Dwarf_Ptr errarg,  
    Dwarf_Debug * dbg,  
    Dwarf_Error *error)
```

The function `dwarf_elf_init()` is identical to `dwarf_init()` except that an open `Elf *` pointer is passed instead of a file descriptor. In systems supporting ELF object files this may be more space or time-efficient than using `dwarf_init()`. The client is allowed to use the `Elf *` pointer for its own purposes without restriction during the time the `Dwarf_Debug` is open, except that the client should not `elf_end()` the pointer till after `dwarf_finish` is called.

### 5.1.3 dwarf\_get\_elf()

```
int dwarf_get_elf(  
    Dwarf_Debug dbg,  
    Elf **      elf,  
    Dwarf_Error *error)
```

When it returns DW\_DLV\_OK, the function `dwarf_get_elf()` returns through the pointer `elf` the `Elf`

\* handle used to access the object represented by the Dwarf\_Debug descriptor dbg. It returns DW\_DLV\_ERROR on error.

Because `int dwarf_init()` opens an Elf descriptor on its fd and `dwarf_finish()` does not close that descriptor, an app should use `dwarf_get_elf` and should call `elf_end` with the pointer returned through the `Elf**` handle created by `int dwarf_init()`.

This function is not meaningful for a system that does not use the Elf format for objects.

#### 5.1.4 dwarf\_finish()

```
int dwarf_finish(  
    Dwarf_Debug dbg,  
    Dwarf_Error *error)
```

The function `dwarf_finish()` releases all *Libdwarf* internal resources associated with the descriptor `dbg`, and invalidates `dbg`. It returns `DW_DLV_ERROR` if there is an error during the finishing operation. It returns `DW_DLV_OK` for a successful operation.

Because `int dwarf_init()` opens an Elf descriptor on its fd and `dwarf_finish()` does not close that descriptor, an app should use `dwarf_get_elf` and should call `elf_end` with the pointer returned through the `Elf**` handle created by `int dwarf_init()`.

#### 5.1.5 dwarf\_set\_stringcheck()

```
int dwarf_set_stringcheck(  
    int stringcheck)
```

The function `int dwarf_set_stringcheck()` sets a global flag and returns the previous value of the global flag.

If the `stringcheck` global flag is zero (the default) *libdwarf* does string length validity checks (the checks do slow *libdwarf* down very slightly). If the `stringcheck` global flag is non-zero *libdwarf* does not do string length validity checks.

The global flag is really just 8 bits long, upperbits are not noticed or recorded.

#### 5.1.6 dwarf\_set\_reloc\_application()

```
int dwarf_set_reloc_application(  
    int apply)
```

The function `int dwarf_set_reloc_application()` sets a global flag and returns the previous value of the global flag.

If the `reloc_application` global flag is non-zero (the default) then the applicable `.rela` section (if one exists) will be processed and applied to any DWARF section when it is read in. If the `reloc_application` global flag is zero no such relocation-application is attempted.

Not all machine types (elf header `e_machine`) or all relocations are supported, but then very few relocation types apply to DWARF debug sections.

The global flag is really just 8 bits long, upperbits are not noticed or recorded.

It seems unlikely anyone will need to call this function.

### 5.1.7 dwarf\_record\_cmdline\_options()

```
int dwarf_record_cmdline_options(  
    Dwarf_Cmdline_Options options)
```

The function `int dwarf_record_cmdline_options()` copies a `Dwarf_Cmdline_Options` structure from consumer code to `libdwf`.

The structure is defined in `libdwf.h`.

The initial version of this structure has a single field `check_verbose_mode` which, if non-zero, tells `libdwf` to print some detailed messages to `stdout` in case certain errors are detected.

The default for this value is `FALSE (0)` so the extra messages are off by default.

## 5.2 Section size operations

These operations are informative but not normally needed.

### 5.2.1 dwarf\_get\_section\_max\_offsets\_b()

```
int dwarf_get_section_max_offsets_b(Dwarf_debug dbg,  
    Dwarf_Unsigned * /*debug_info_size*/,  
    Dwarf_Unsigned * /*debug_abbrev_size*/,  
    Dwarf_Unsigned * /*debug_line_size*/,  
    Dwarf_Unsigned * /*debug_loc_size*/,  
    Dwarf_Unsigned * /*debug_aranges_size*/,  
    Dwarf_Unsigned * /*debug_macinfo_size*/,  
    Dwarf_Unsigned * /*debug_pubnames_size*/,  
    Dwarf_Unsigned * /*debug_str_size*/,  
    Dwarf_Unsigned * /*debug_frame_size*/,  
    Dwarf_Unsigned * /*debug_ranges_size*/,  
    Dwarf_Unsigned * /*debug_pubtypes_size*/,  
    Dwarf_Unsigned * /*debug_types_size*/);
```

The function `dwarf_get_section_max_offsets_b()` an open `Dwarf_Dbg` and reports on the section sizes by pushing section size values back through the pointers.

Created in October 2011.

### 5.2.2 dwarf\_get\_section\_max\_offsets()

```
int dwarf_get_section_max_offsets(Dwarf_debug dbg,  
    Dwarf_Unsigned * /*debug_info_size*/,  
    Dwarf_Unsigned * /*debug_abbrev_size*/,  
    Dwarf_Unsigned * /*debug_line_size*/,  
    Dwarf_Unsigned * /*debug_loc_size*/,  
    Dwarf_Unsigned * /*debug_aranges_size*/,  
    Dwarf_Unsigned * /*debug_macinfo_size*/,  
    Dwarf_Unsigned * /*debug_pubnames_size*/,  
    Dwarf_Unsigned * /*debug_str_size*/,  
    Dwarf_Unsigned * /*debug_frame_size*/,  
    Dwarf_Unsigned * /*debug_ranges_size*/,  
    Dwarf_Unsigned * /*debug_pubtypes_size*/);
```

The function is the same as `dwarf_get_section_max_offsets_b()` except it is missing the

`debug_types_size()` argument. Though obsolete it is still supported.

## 5.3 Printf Callbacks

This is new in August 2013.

The `dwarf_print_lines()` function is intended as a helper to programs like `dwarfdump` and show some line internal details in a way only the internals of `libdwarf` can show these details. But using `printf` directly in `libdwarf` means the caller has limited control of where the output appears. So now the 'printf' output is passed back to the caller through a callback function whose implementation is provided by the caller.

Any code calling `libdwarf` can ignore the functions described in this section completely. If the functions are ignored the messages (if any) from `libdwarf` will simply not appear anywhere.

The `libdwarf.h` header file defines `struct Dwarf_Printf_Callback_Info_s` and `dwarf_register_printf_callback` for those `libdwarf` callers wishing to implement the callback. In this section we describe how one uses that interface. The applications `dwarfdump` and `dwarfdump2` are examples of how these may be used.

### 5.3.1 dwarf\_register\_printf\_callback

```
struct Dwarf_Printf_Callback_Info_s
    dwarf_register_printf_callback(Dwarf_Debug dbg,
        struct Dwarf_Printf_Callback_Info_s * newvalues);
```

The `dwarf_register_printf_callback()` function can only be called after the `Dwarf_Debug` instance has been initialized, the call makes no sense at other times. The function returns the current value of the structure. If `newvalues` is non-null then the passed-in values are used to initialize the `libdwarf` internal callback data (the values returned are the values before the `newvalues` are recorded). If `newvalues` is null no change is made to the `libdwarf` internal callback data.

### 5.3.2 Dwarf\_Printf\_Callback\_Info\_s

```
struct Dwarf_Printf_Callback_Info_s {
    void *                dp_user_pointer;
    dwarf_printf_callback_function_type dp_fptr;
    char *                dp_buffer;
    unsigned int          dp_buffer_len;
    int                   dp_buffer_user_provided;
    void *                dp_reserved;
};
```

First we describe the fields as applicable in setting up for a call to `dwarf_register_printf_callback()`.

The field `dp_user_pointer` is remembered by `libdwarf` and passed back in any call `libdwarf` makes to the user's callback function. It is otherwise ignored by `libdwarf`.

The field `dp_fptr` is either `NULL` or a pointer to a user-implemented function.

If the field `dp_buffer_user_provided` is non-zero then `dp_buffer_len` and `dp_buffer` must be set by the user and `libdwarf` will use that buffer without doing any malloc of space. If the field

dp\_buffer\_user\_provided is zero then the input fields dp\_buffer\_len and dp\_buffer are ignored by libdwarf and space is malloc'd as needed.

The field dp\_reserved is ignored, it is reserved for future use.

When the structure is returned by dwarf\_register\_printf\_callback() the values of the fields before the dwarf\_register\_printf\_callback() call are returned.

### 5.3.3 dwarf\_printf\_callback\_function\_type

```
typedef void (* dwarf_printf_callback_function_type)(void * user_pointer,  
    const char * linecontent);
```

Any application using the callbacks needs to use the function dwarf\_register\_printf\_callback() and supply a function matching the above function prototype from libdwarf.h.

### 5.3.4 Example of printf callback use in a C++ application using libdwarf

```
struct Dwarf_Printf_Callback_Info_s printfcallbackdata;  
    memset(&printfcallbackdata,0,sizeof(printfcallbackdata));  
    printfcallbackdata.dp_fptr = printf_callback_for_libdwarf;  
    dwarf_register_printf_callback(dbg,&printfcallbackdata);
```

Assuming the user implements something like the following function in her application:

```
void  
printf_callback_for_libdwarf(void *userdata,const char *data)  
{  
    cout << data;  
}
```

It is crucial that the user's callback function copies or prints the data immediately. Once the user callback function returns the data pointer may change or become stale without warning.

## 5.4 Debugging Information Entry Delivery Operations

These functions are concerned with accessing debugging information entries.

### 5.4.1 dwarf\_next\_cu\_header\_c()

```
int dwarf_next_cu_header_c(  
    Dwarf_Debug dbg,  
    Dwarf_Bool is_info,  
    Dwarf_Unsigned *cu_header_length,  
    Dwarf_Half *version_stamp,  
    Dwarf_Unsigned *abbrev_offset,  
    Dwarf_Half *address_size,  
    Dwarf_Half *offset_size,  
    Dwarf_Half *extension_size,  
    Dwarf_Sig8 *signature,  
    Dwarf_Unsigned *typeoffset,  
    Dwarf_Unsigned *next_cu_header,  
    Dwarf_Error *error);
```

The function `dwarf_next_cu_header_c()` operates on either the `.debug_info` section (if `is_info` is non-zero) or `.debug_types` section (if `is_info` is zero). It returns `DW_DLV_ERROR` if it fails, and `DW_DLV_OK` if it succeeds.

If it succeeds, `*next_cu_header` is set to the offset in the `.debug_info` section of the next compilation-unit header if it succeeds. On reading the last compilation-unit header in the `.debug_info` section it contains the size of the `.debug_info` or `debug_types` section. The next call to `dwarf_next_cu_header_b()` returns `DW_DLV_NO_ENTRY` without reading a compilation-unit or setting `*next_cu_header`. Subsequent calls to `dwarf_next_cu_header()` repeat the cycle by reading the first compilation-unit and so on.

The other values returned through pointers are the values in the compilation-unit header. If any of `cu_header_length`, `version_stamp`, `abbrev_offset`, `address_size`, `offset_size`, `extension_size`, `signature`, or `typeoffset`, is NULL, the argument is ignored (meaning it is not an error to provide a NULL pointer for any or all of these arguments).

`cu_header_length` returns the length in bytes of the compilation unit header.

`version_stamp` returns the section version, which would be (for `.debug_info`) 2 for DWARF2, 3 for DWARF3, or 4 for DWARF4.

`abbrev_offset` returns the `.debug_abbrev` section offset of the abbreviations for this compilation unit.

`address_size` returns the size of an address in this compilation unit. Which is usually 4 or 8.

`offset_size` returns the size in bytes of an offset for the compilation unit. The offset size is 4 for 32bit dwarf and 8 for 64bit dwarf. This is the offset size in dwarf data, not the address size inside the executable code. The offset size can be 4 even if embedded in a 64bit elf file (which is normal for 64bit elf), and can be 8 even in a 32bit elf file (which probably will never be seen in practice).

The `extension_size` pointer is only relevant if the `offset_size` pointer returns 8. The value is not normally useful but is returned through the pointer for completeness. The pointer `extension_size` returns 0 if the CU is MIPS/IRIX non-standard 64bit dwarf (MIPS/IRIX 64bit dwarf was created years before DWARF3 defined 64bit dwarf) and returns 4 if the dwarf uses the standard 64bit extension (the 4 is the size in bytes of the 0xffffffff in the initial length field which indicates the following 8 bytes in the `.debug_info` section are the real length). See the DWARF3 or DWARF4 standard, section 7.4.

The `signature` pointer is only relevant if `is_info` is zero, and if relevant the 8 byte type signature of the `.debug_types` CU header is assigned through the pointer.

The `typeoffset` pointer is only relevant if `is_info` is zero, and if relevant the local offset within the CU of the type offset the `.debug_types` entry represents is assigned through the pointer. The `typeoffset` matters because a `DW_AT_type` referencing the type unit may reference an inner type, such as a C++ class in a C++ namespace, but the type itself has the enclosing namespace in the `.debug_type` unit.

### 5.4.2 dwarf\_next\_cu\_header\_b()

```
int dwarf_next_cu_header_b(
    Dwarf_Debug dbg,
    Dwarf_Unsigned *cu_header_length,
    Dwarf_Half     *version_stamp,
    Dwarf_Unsigned *abbrev_offset,
    Dwarf_Half     *address_size,
    Dwarf_Half     *offset_size,
    Dwarf_Half     *extension_size,
    Dwarf_Unsigned *next_cu_header,
    Dwarf_Error    *error);
```

This is obsolete as of October 2011 though supported.

The function `dwarf_next_cu_header_b()` operates on the `.debug_info` section. It operates exactly like `dwarf_next_cu_header_c()` but is missing the `signature`, and `typeoffset` fields. This is kept for compatibility. All code using this should be changed to use `dwarf_next_cu_header_c()`

### 5.4.3 dwarf\_next\_cu\_header()

The following is the original form, missing the `offset_size`, `extension_size`, `signature`, and `typeoffset` fields in `dwarf_next_cu_header_c()`. This is kept for compatibility. All code using this should be changed to use `dwarf_next_cu_header_c()`

```
int dwarf_next_cu_header(
    Dwarf_Debug dbg,
    Dwarf_Unsigned *cu_header_length,
    Dwarf_Half     *version_stamp,
    Dwarf_Unsigned *abbrev_offset,
    Dwarf_Half     *address_size,
    Dwarf_Unsigned *next_cu_header,
    Dwarf_Error    *error);
```

### 5.4.4 dwarf\_siblingof\_b()

```
int dwarf_siblingof_b(
    Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Bool is_info,
    Dwarf_Die *return_sib,
    Dwarf_Error *error)
```

The function `dwarf_siblingof_b()` returns `DW_DLV_ERROR` and sets the error pointer on error. If there is no sibling it returns `DW_DLV_NO_ENTRY`. When it succeeds, `dwarf_siblingof_b()` returns `DW_DLV_OK` and sets `*return_sib` to the `Dwarf_Die` descriptor of the sibling of `die`.

If `is_info` is non-zero then the `die` is assumed to refer to a `.debug_info` DIE. If `is_info` is zero then the `die` is assumed to refer to a `.debug_types` DIE. Note that the first call (the call that gets the compilation-unit DIE in a compilation unit) passes in a `NULL` `die` so having the caller pass in `is_info` is essential. And if `die` is non-`NULL` it is still essential for the call to pass in `is_info` set properly to reflect the section the DIE came from. The function `dwarf_get_die_infotypes_flag()` is of interest as it returns the proper `is_info` value from any non-`NULL` `die` pointer.

If `die` is `NULL`, the `Dwarf_Die` descriptor of the first die in the compilation-unit is returned. This die



has the DW\_TAG\_compile\_unit, DW\_TAG\_partial\_unit, or DW\_TAG\_type\_unit tag.

```
Dwarf_Die return_sib = 0;
Dwarf_Error error = 0;
int res;
Dwarf_Bool is_info = 1;
/* in_die might be NULL or a valid Dwarf_Die */
res = dwarf_siblingof_b(dbg, in_die, is_info, &return_sib, &error);
if (res == DW_DLV_OK) {
    /* Use return_sib here. */
    dwarf_dealloc(dbg, return_sib, DW_DLA_DIE);
    /* return_sib is no longer usable for anything, we
       ensure we do not use it accidentally with: */
    return_sib = 0;
}
```

#### 5.4.5 dwarf\_siblingof()

```
int dwarf_siblingof(
    Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Die *return_sib,
    Dwarf_Error *error)
```

int dwarf\_siblingof() operates exactly the same as int dwarf\_siblingof\_b(), but int dwarf\_siblingof() refers only to .debug\_info DIEs.

#### 5.4.6 dwarf\_child()

```
int dwarf_child(
    Dwarf_Die die,
    Dwarf_Die *return_kid,
    Dwarf_Error *error)
```

The function dwarf\_child() returns DW\_DLV\_ERROR and sets the error die on error. If there is no child it returns DW\_DLV\_NO\_ENTRY. When it succeeds, dwarf\_child() returns DW\_DLV\_OK and sets \*return\_kid to the Dwarf\_Die descriptor of the first child of die. The function dwarf\_siblingof() can be used with the return value of dwarf\_child() to access the other children of die.

```
Dwarf_Die return_kid = 0;
Dwarf_Error error = 0;
int res;

res = dwarf_child(dbg, in_die, &return_kid, &error);
if (res == DW_DLV_OK) {
    /* Use return_kid here. */
    dwarf_dealloc(dbg, return_kid, DW_DLA_DIE);
    /* return_die is no longer usable for anything, we
       ensure we do not use it accidentally with: */
    return_kid = 0;
}
```

### 5.4.7 dwarf\_offdie\_b()

```
int dwarf_offdie_b(  
    Dwarf_Debug dbg,  
    Dwarf_Off offset,  
    Dwarf_Bool is_info,  
    Dwarf_Die *return_die,  
    Dwarf_Error *error)
```

The function `dwarf_offdie_b()` returns `DW_DLV_ERROR` and sets the error die on error. When it succeeds, `dwarf_offdie_b()` returns `DW_DLV_OK` and sets `*return_die` to the the `Dwarf_Die` descriptor of the debugging information entry at `offset` in the section containing debugging information entries i.e the `.debug_info` section. A return of `DW_DLV_NO_ENTRY` means that the `offset` in the section is of a byte containing all 0 bits, indicating that there is no abbreviation code. Meaning this 'die offset' is not the offset of a real die, but is instead an offset of a null die, a padding die, or of some random zero byte: this should not be returned in normal use.

It is the user's responsibility to make sure that `offset` is the start of a valid debugging information entry. The result of passing it an invalid offset could be chaos.

If `is_info` is non-zero the `offset` must refer to a `.debug_info` section offset. If `is_info` zero the `offset` must refer to a `.debug_types` section offset. Error returns or misleading values may result if the `is_info` flag or the `offset` value are incorrect.

```
Dwarf_Error error = 0;  
Dwarf_Die return_die = 0;  
int res;  
  
res = dwarf_offdie_b(dbg,die_offset,&return_die, &error);  
if (res == DW_DLV_OK) {  
    /* Use return_die here. */  
    dwarf_dealloc(dbg, return_die, DW_DLA_DIE);  
    /* return_die is no longer usable for anything, we  
       ensure we do not use it accidentally with: */  
    return_die = 0;  
}
```

### 5.4.8 dwarf\_offdie()

```
int dwarf_offdie(  
    Dwarf_Debug dbg,  
    Dwarf_Off offset,  
    Dwarf_Die *return_die,  
    Dwarf_Error *error)
```

The function `dwarf_offdie()` is obsolete, use `dwarf_offdie_b()` instead. The function is still supported in the library, but only references the `.debug_info` section.

### 5.4.9 dwarf\_validate\_die\_sibling()

```
int validate_die_sibling(  
    Dwarf_Die sibling,  
    Dwarf_Off *offset)
```

When used correctly in a depth-first walk of a DIE tree this function validates that any `DW_AT_sibling`

attribute gives the same offset as the direct tree walk. That is the only purpose of this function.

The function `dwarf_validate_die_sibling()` returns `DW_DLV_OK` if the last die processed in a depth-first DIE tree walk was the same offset as generated by a call to `dwarf_siblingof()`. Meaning that the `DW_AT_sibling` attribute value, if any, was correct.

If the conditions are not met then `DW_DLV_ERROR` is returned and `*offset` is set to the offset in the `.debug_info` section of the last DIE processed. If the application prints the offset a knowledgeable user may be able to figure out what the compiler did wrong.

## 5.5 Debugging Information Entry Query Operations

These queries return specific information about debugging information entries or a descriptor that can be used on subsequent queries when given a `Dwarf_Die` descriptor. Note that some operations are specific to debugging information entries that are represented by a `Dwarf_Die` descriptor of a specific type. For example, not all debugging information entries contain an attribute having a name, so consequently, a call to `dwarf_diename()` using a `Dwarf_Die` descriptor that does not have a name attribute will return `DW_DLV_NO_ENTRY`. This is not an error, i.e. calling a function that needs a specific attribute is not an error for a die that does not contain that specific attribute.

There are several methods that can be used to obtain the value of an attribute in a given die:

1. Call `dwarf_hasattr()` to determine if the debugging information entry has the attribute of interest prior to issuing the query for information about the attribute.
2. Supply an `error` argument, and check its value after the call to a query indicates an unsuccessful return, to determine the nature of the problem. The `error` argument will indicate whether an error occurred, or the specific attribute needed was missing in that die.
3. Arrange to have an error handling function invoked upon detection of an error (see `dwarf_init()`).
4. Call `dwarf_attrlist()` and iterate through the returned list of attributes, dealing with each one as appropriate.

### 5.5.1 dwarf\_get\_die\_infotypes\_flag()

`Dwarf_Bool dwarf_get_die_infotypes_flag(Dwarf_Die die)`

The function `dwarf_tag()` returns the section flag indicating which section the DIE originates from. If the returned value is non-zero the DIE originates from the `.debug_info` section. If the returned value is zero the DIE originates from the `.debug_types` section.

### 5.5.2 dwarf\_tag()

```
int dwarf_tag(  
    Dwarf_Die die,  
    Dwarf_Half *tagval,  
    Dwarf_Error *error)
```

The function `dwarf_tag()` returns the `tag` of `die` through the pointer `tagval` if it succeeds. It returns `DW_DLV_OK` if it succeeds. It returns `DW_DLV_ERROR` on error.

### 5.5.3 dwarf\_dieoffset()

```
int dwarf_dieoffset(  
    Dwarf_Die die,  
    Dwarf_Off * return_offset,  
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_dieoffset()` returns `DW_DLV_OK` and sets `*return_offset` to the position of `die` in the section containing debugging information entries (the `return_offset` is a section-relative offset). In other words, it sets `return_offset` to the offset of the start of the debugging information entry described by `die` in the section containing dies i.e `.debug_info`. It returns `DW_DLV_ERROR` on error.

### 5.5.4 dwarf\_die\_CU\_offset()

```
int dwarf_die_CU_offset(  
    Dwarf_Die die,  
    Dwarf_Off *return_offset,  
    Dwarf_Error *error)
```

The function `dwarf_die_CU_offset()` is similar to `dwarf_dieoffset()`, except that it puts the offset of the DIE represented by the `Dwarf_Die die`, from the start of the compilation-unit that it belongs to rather than the start of `.debug_info` (the `return_offset` is a CU-relative offset).

### 5.5.5 dwarf\_die\_offsets()

```
int dwarf_die_offsets(  
    Dwarf_Die die,  
    Dwarf_Off *global_off,  
    Dwarf_Off *cu_off,  
    Dwarf_Error *error)
```

The function `dwarf_die_offsets()` is a combination of `dwarf_dieoffset()` and `dwarf_die_CU_offset()` in that it returns both the global `.debug_info` offset and the CU-relative offset of the die in a single call.

### 5.5.6 dwarf\_ptr\_CU\_offset()

```
int dwarf_ptr_CU_offset(  
    Dwarf_CU_Context cu_context,  
    Dwarf_Byte_ptr di_ptr ,  
    Dwarf_Off *cu_off)
```

Given a valid CU context pointer and a pointer into that CU context, the function `dwarf_ptr_CU_offset()` returns `DW_DLV_OK` and sets `*cu_off` to the CU-relative (local) offset in that CU.

### 5.5.7 dwarf\_CU\_dieoffset\_given\_die()

```
int dwarf_CU_dieoffset_given_die(  
    Dwarf_Die given_die,  
    Dwarf_Off *return_offset,  
    Dwarf_Error *error)
```

The function `dwarf_CU_dieoffset_given_die()` is similar to `dwarf_die_CU_offset()`, except that it puts the global offset of the CU DIE owning `given_die` of `.debug_info` (the `return_offset` is a global section offset).

This is useful when processing a DIE tree and encountering an error or other surprise in a DIE, as the `return_offset` can be passed to `dwarf_offdie_b()` to return a pointer to the CU die of the CU owning the `given_die` passed to `dwarf_CU_dieoffset_given_die()`. The consumer can extract information from the CU die and the `given_die` (in the normal way) and print it.

An example (a snippet) of code using this function follows. It assumes that `in_die` is a DIE that, for some reason, you have decided needs CU context printed (assuming `print_die_data` does some reasonable printing).

```
int res;
Dwarf_Off cudieoff = 0;
Dwarf_Die cudie = 0;

print_die_data(dbg,in_die);
res = dwarf_CU_dieoffset_given_die(in_die,&cudieoff,&error);
if(res != DW_DLV_OK) {
    printf("FAIL: dwarf_CU_dieoffset_given_die did not work0);
    exit(1);
}
res = dwarf_offdie_b(dbg,cudieoff,&cudie,&error);
if(res != DW_DLV_OK) {
    printf("FAIL: dwarf_offdie did not work0);
    exit(1);
}
print_die_data(dbg,cudie);
dwarf_dealloc(dbg,cudie, DW_DLA_DIE);
```

### 5.5.8 dwarf\_die\_CU\_offset\_range()

```
int dwarf_die_CU_offset_range(
    Dwarf_Die die,
    Dwarf_Off *cu_global_offset,
    Dwarf_Off *cu_length,
    Dwarf_Error *error)
```

The function `dwarf_die_CU_offset_range()` returns the offset of the beginning of the CU and the length of the CU. The offset and length are of the entire CU that this DIE is a part of. It is used by `dwarfdump` (for example) to check the validity of offsets. Most applications will have no reason to call this function.

### 5.5.9 dwarf\_diename()

```
int dwarf_diename(
    Dwarf_Die die,
    char ** return_name,
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_diename()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string of characters that represents the name attribute of die. It returns `DW_DLV_NO_ENTRY` if die does not have a name attribute. It returns `DW_DLV_ERROR` if an error occurred. The storage pointed to by a successful return of `dwarf_diename()` should be freed using the allocation type `DW_DLA_STRING` when no longer of interest (see `dwarf_dealloc()`).

#### 5.5.10 dwarf\_die\_abbrev\_code()

```
int dwarf_die_abbrev_code( Dwarf_Die die)
```

The function returns the abbreviation code of the DIE. That is, it returns the abbreviation "index" into the abbreviation table for the compilation unit of which the DIE is a part. It cannot fail. No errors are possible. The pointer `die()` must not be NULL.

#### 5.5.11 dwarf\_die\_abbrev\_children\_flag()

```
int dwarf_die_abbrev_children_flag( Dwarf_Die die,  
    Dwarf_Half *has_child)
```

The function returns the has-children flag of the die passed in through the `*has_child` passed in and returns `DW_DLV_OK` on success. A non-zero value of `*has_child` means the die has children.

On failure it returns `DW_DLV_ERROR`.

The function was developed to let consumer code do better error reporting in some circumstances, it is not generally needed.

#### 5.5.12 dwarf\_get\_version\_of\_die()

```
int dwarf_get_version_of_die(Dwarf_Die die,  
    Dwarf_Half *version,  
    Dwarf_Half *offset_size)
```

The function returns the CU context version through `*version` and the CU context offset-size through `*offset_size` and returns `DW_DLV_OK` on success.

In case of error, the only errors possible involve an inappropriate NULL die pointer so no Dwarf\_Debug pointer is available. Therefore setting a Dwarf\_Error would not be very meaningful (there is no Dwarf\_Debug to attach it to). The function returns `DW_DLV_ERROR` on error.

The values returned through the pointers are the values two arguments to `dwarf_get_form_class()` requires.

#### 5.5.13 dwarf\_attrlist()

```
int dwarf_attrlist(  
    Dwarf_Die die,  
    Dwarf_Attribute** attrbuf,  
    Dwarf_Signed *attrcount,  
    Dwarf_Error *error)
```

When it returns `DW_DLV_OK`, the function `dwarf_attrlist()` sets `attrbuf` to point to an array of Dwarf\_Attribute descriptors corresponding to each of the attributes in die, and returns the number of elements in the array through `attrcount`. `DW_DLV_NO_ENTRY` is returned if the count is zero (no `attrbuf` is allocated in this case). `DW_DLV_ERROR` is returned on error. On a successful return from

`dwarf_attrlist()`, each of the `Dwarf_Attribute` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_ATTR`, followed by free-ing the list pointed to by `*attrbuf` using `dwarf_dealloc()` with the allocation type `DW_DLA_LIST`, when no longer of interest (see `dwarf_dealloc()`).

Freeing the attrlist:

```
Dwarf_Unsigned atcnt;
Dwarf_Attribute *atlist;
int errv;

errv = dwarf_attrlist(somedie, &atlist, &atcnt, &error);
if (errv == DW_DLV_OK) {

    for (i = 0; i < atcnt; ++i) {
        /* use atlist[i] */
        dwarf_dealloc(dbg, atlist[i], DW_DLA_ATTR);
    }
    dwarf_dealloc(dbg, atlist, DW_DLA_LIST);
}
```

#### 5.5.14 dwarf\_hasattr()

```
int dwarf_hasattr(
    Dwarf_Die die,
    Dwarf_Half attr,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_hasattr()` returns `DW_DLV_OK` and sets `*return_bool` to *non-zero* if `die` has the attribute `attr` and *zero* otherwise. If it fails, it returns `DW_DLV_ERROR`.

#### 5.5.15 dwarf\_attr()

```
int dwarf_attr(
    Dwarf_Die die,
    Dwarf_Half attr,
    Dwarf_Attribute *return_attr,
    Dwarf_Error *error)
```

When it returns `DW_DLV_OK`, the function `dwarf_attr()` sets `*return_attr` to the `Dwarf_Attribute` descriptor of `die` having the attribute `attr`. It returns `DW_DLV_NO_ENTRY` if `attr` is not contained in `die`. It returns `DW_DLV_ERROR` if an error occurred.

#### 5.5.16 dwarf\_lowpc()

```
int dwarf_lowpc(
    Dwarf_Die die,
    Dwarf_Addr * return_lowpc,
    Dwarf_Error * error)
```

The function `dwarf_lowpc()` returns `DW_DLV_OK` and sets `*return_lowpc` to the low program counter value associated with the `die` descriptor if `die` represents a debugging information entry with the `DW_AT_low_pc` attribute. It returns `DW_DLV_NO_ENTRY` if `die` does not have this attribute. It returns `DW_DLV_ERROR` if an error occurred.

### 5.5.17 dwarf\_highpc\_b()

```
int dwarf_highpc_b(  
    Dwarf_Die          die,  
    Dwarf_Addr *      return_highpc,  
    Dwarf_Half *      return_form*,  
    enum Dwarf_Form_Class * return_class*,  
    Dwarf_Error *error)
```

The function `dwarf_highpc_b()` returns `DW_DLV_OK` and sets `*return_highpc` to the value of the `DW_AT_high_pc` attribute. It also sets `return_form` to the FORM of the attribute. It also sets `return_class` to the form class of the attribute.

If the form class returned is `DW_FORM_CLASS_ADDRESS` the `return_highpc` is an actual pc address (1 higher than the address of the last pc in the address range).. If the form class returned is `DW_FORM_CLASS_CONSTANT` the `return_highpc` is an offset from the value of the the DIE's low PC address (see DWARF4 section 2.17.2 Contiguous Address Range).

It returns `DW_DLV_NO_ENTRY` if `die` does not have the `DW_AT_high_pc` attribute.

It returns `DW_DLV_ERROR` if an error occurred.

### 5.5.18 dwarf\_highpc()

```
int dwarf_highpc(  
    Dwarf_Die die,  
    Dwarf_Addr * return_highpc,  
    Dwarf_Error *error)
```

The function `dwarf_highpc()` returns `DW_DLV_OK` and sets `*return_highpc` the high program counter value associated with the `die` descriptor if `die` represents a debugging information entry with the `DW_AT_high_pc` attribute and the form is `DW_FORM_addr` (meaning the form is of class address).

This function is useless for a `DW_AT_high_pc` which is encoded as a constant (which was first possible in DWARF4).

It returns `DW_DLV_NO_ENTRY` if `die` does not have this attribute.

It returns `DW_DLV_ERROR` if an error occurred or if the form is not of class address.

### 5.5.19 dwarf\_bytesize()

```
Dwarf_Signed dwarf_bytesize(  
    Dwarf_Die die,  
    Dwarf_Unsigned *return_size,  
    Dwarf_Error *error)
```

When it succeeds, `dwarf_bytesize()` returns `DW_DLV_OK` and sets `*return_size` to the number of bytes needed to contain an instance of the aggregate debugging information entry represented by `die`. It returns `DW_DLV_NO_ENTRY` if `die` does not contain the byte size attribute `DW_AT_byte_size`. It returns `DW_DLV_ERROR` if an error occurred.



### 5.5.20 dwarf\_bitsize()

```
int dwarf_bitsize(  
    Dwarf_Die die,  
    Dwarf_Unsigned *return_size,  
    Dwarf_Error *error)
```

When it succeeds, `dwarf_bitsize()` returns `DW_DLV_OK` and sets `*return_size` to the number of bits occupied by the bit field value that is an attribute of the given die. It returns `DW_DLV_NO_ENTRY` if die does not contain the bit size attribute `DW_AT_bit_size`. It returns `DW_DLV_ERROR` if an error occurred.

### 5.5.21 dwarf\_bitoffset()

```
int dwarf_bitoffset(  
    Dwarf_Die die,  
    Dwarf_Unsigned *return_size,  
    Dwarf_Error *error)
```

When it succeeds, `dwarf_bitoffset()` returns `DW_DLV_OK` and sets `*return_size` to the number of bits to the left of the most significant bit of the bit field value. This bit offset is not necessarily the net bit offset within the structure or class, since `DW_AT_data_member_location` may give a byte offset to this DIE and the bit offset returned through the pointer does not include the bits in the byte offset. It returns `DW_DLV_NO_ENTRY` if die does not contain the bit offset attribute `DW_AT_bit_offset`. It returns `DW_DLV_ERROR` if an error occurred.

### 5.5.22 dwarf\_srclang()

```
int dwarf_srclang(  
    Dwarf_Die die,  
    Dwarf_Unsigned *return_lang,  
    Dwarf_Error *error)
```

When it succeeds, `dwarf_srclang()` returns `DW_DLV_OK` and sets `*return_lang` to a code indicating the source language of the compilation unit represented by the descriptor die. It returns `DW_DLV_NO_ENTRY` if die does not represent a source file debugging information entry (i.e. contain the attribute `DW_AT_language`). It returns `DW_DLV_ERROR` if an error occurred.

### 5.5.23 dwarf\_arrayorder()

```
int dwarf_arrayorder(  
    Dwarf_Die die,  
    Dwarf_Unsigned *return_order,  
    Dwarf_Error *error)
```

When it succeeds, `dwarf_arrayorder()` returns `DW_DLV_OK` and sets `*return_order` a code indicating the ordering of the array represented by the descriptor die. It returns `DW_DLV_NO_ENTRY` if die does not contain the array order attribute `DW_AT_ordering`. It returns `DW_DLV_ERROR` if an error occurred.

## 5.6 Attribute Queries

Based on the attributes form, these operations are concerned with returning uninterpreted attribute data. Since it is not always obvious from the return value of these functions if an error occurred, one should always supply an error parameter or have arranged to have an error handling function invoked (see `dwarf_init()`) to determine the validity of the returned value and the nature of any errors that may have

occurred.

A `Dwarf_Attribute` descriptor describes an attribute of a specific die. Thus, each `Dwarf_Attribute` descriptor is implicitly associated with a specific die.

### 5.6.1 dwarf\_hasform()

```
int dwarf_hasform(
    Dwarf_Attribute attr,
    Dwarf_Half form,
    Dwarf_Bool *return_hasform,
    Dwarf_Error *error)
```

The function `dwarf_hasform()` returns `DW_DLV_OK` and puts a *non-zero* value in the `*return_hasform` boolean if the attribute represented by the `Dwarf_Attribute` descriptor `attr` has the attribute form `form`. If the attribute does not have that form *zero* is put into `*return_hasform`. `DW_DLV_ERROR` is returned on error.

### 5.6.2 dwarf\_whatform()

```
int dwarf_whatform(
    Dwarf_Attribute attr,
    Dwarf_Half *return_form,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_whatform()` returns `DW_DLV_OK` and sets `*return_form` to the attribute form code of the attribute represented by the `Dwarf_Attribute` descriptor `attr`. It returns `DW_DLV_ERROR` on error.

An attribute using `DW_FORM_indirect` effectively has two forms. This function returns the 'final' form for `DW_FORM_indirect`, not the `DW_FORM_indirect` itself. This function is what most applications will want to call.

### 5.6.3 dwarf\_whatform\_direct()

```
int dwarf_whatform_direct(
    Dwarf_Attribute attr,
    Dwarf_Half *return_form,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_whatform_direct()` returns `DW_DLV_OK` and sets `*return_form` to the attribute form code of the attribute represented by the `Dwarf_Attribute` descriptor `attr`. It returns `DW_DLV_ERROR` on error. An attribute using `DW_FORM_indirect` effectively has two forms. This returns the form 'directly' in the initial form field. That is, it returns the 'initial' form of the attribute.

So when the form field is `DW_FORM_indirect` this call returns the `DW_FORM_indirect` form, which is sometimes useful for dump utilities.

It is confusing that the `_direct()` function returns `DW_FORM_indirect` if an indirect form is involved. Just think of this as returning the initial form the first form value seen for the attribute, which is also the final form unless the initial form is `DW_FORM_indirect`.

### 5.6.4 dwarf\_whatattr()

```
int dwarf_whatattr(  
    Dwarf_Attribute attr,  
    Dwarf_Half      *return_attr,  
    Dwarf_Error     *error)
```

When it succeeds, `dwarf_whatattr()` returns `DW_DLV_OK` and sets `*return_attr` to the attribute code represented by the `Dwarf_Attribute` descriptor `attr`. It returns `DW_DLV_ERROR` on error.

### 5.6.5 dwarf\_formref()

```
int dwarf_formref(  
    Dwarf_Attribute attr,  
    Dwarf_Off       *return_offset,  
    Dwarf_Error     *error)
```

When it succeeds, `dwarf_formref()` returns `DW_DLV_OK` and sets `*return_offset` to the CU-relative offset represented by the descriptor `attr` if the form of the attribute belongs to the `REFERENCE` class. `attr` must be a CU-local reference, not form `DW_FORM_ref_addr` and not `DW_FORM_sec_offset`. It is an error for the form to not belong to the `REFERENCE` class. It returns `DW_DLV_ERROR` on error.

Beginning November 2010: All `DW_DLV_ERROR` returns set `*return_offset`. Most errors set `*return_offset` to zero, but for error `DW_DLE_ATTR_FORM_OFFSET_BAD` the function sets `*return_offset` to the invalid offset (which allows the caller to print a more detailed error message).

See also `dwarf_global_formref` below.

### 5.6.6 dwarf\_global\_formref()

```
int dwarf_global_formref(  
    Dwarf_Attribute attr,  
    Dwarf_Off       *return_offset,  
    Dwarf_Error     *error)
```

When it succeeds, `dwarf_global_formref()` returns `DW_DLV_OK` and sets `*return_offset` to the section-relative offset represented by the descriptor `attr` if the form of the attribute belongs to the `REFERENCE` or other section-references classes.

`attr` can be any legal `REFERENCE` class form plus `DW_FORM_ref_addr` or `DW_FORM_sec_offset`. It is an error for the form to not belong to one of the reference classes. It returns `DW_DLV_ERROR` on error. See also `dwarf_formref` above.

The caller must determine which section the offset returned applies to. The function `dwarf_get_form_class()` is useful to determine the applicable section.

The function converts CU relative offsets from forms such as `DW_FORM_ref4` into global section offsets.

### 5.6.7 dwarf\_convert\_to\_global\_offset()

```
int dwarf_convert_to_global_offset(  
    Dwarf_Attribute attr,  
    Dwarf_Off       offset,  
    Dwarf_Off       *return_offset,  
    Dwarf_Error     *error)
```

When it succeeds, `dwarf_convert_to_global_offset()` returns `DW_DLV_OK` and sets

`*return_offset` to the section-relative offset represented by the cu-relative offset `offset` if the form of the attribute belongs to the REFERENCE class. `attr` must be a CU-local reference (DWARF class REFERENCE) or form DW\_FORM\_ref\_addr and the `attr` must be directly relevant for the calculated `*return_offset` to mean anything.

The function returns DW\_DLV\_ERROR on error.

The function is not strictly necessary but may be a convenience for attribute printing in case of error.

### 5.6.8 dwarf\_formaddr()

```
int dwarf_formaddr(
    Dwarf_Attribute attr,
    Dwarf_Addr      * return_addr,
    Dwarf_Error     *error)
```

When it succeeds, `dwarf_formaddr()` returns DW\_DLV\_OK and sets `*return_addr` to the address represented by the descriptor `attr` if the form of the attribute belongs to the ADDRESS class. It is an error for the form to not belong to this class. It returns DW\_DLV\_ERROR on error.

### 5.6.9 dwarf\_formflag()

```
int dwarf_formflag(
    Dwarf_Attribute attr,
    Dwarf_Bool      * return_bool,
    Dwarf_Error     *error)
```

When it succeeds, `dwarf_formflag()` returns DW\_DLV\_OK and sets `*return_bool` to the (one unsigned byte) flag value. Any non-zero value means true. A zero value means false.

Before 29 November 2012 this would only return 1 or zero through the pointer, but that was always a strange thing to do. The DWARF specification has always been clear that any non-zero value means true. The function should report the value found truthfully, and now it does.

It returns DW\_DLV\_ERROR on error or if the `attr` does not have form flag.

### 5.6.10 dwarf\_formudata()

```
int dwarf_formudata(
    Dwarf_Attribute attr,
    Dwarf_Unsigned  * return_uvalue,
    Dwarf_Error     * error)
```

The function `dwarf_formudata()` returns DW\_DLV\_OK and sets `*return_uvalue` to the Dwarf\_Unsigned value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the CONSTANT class. It is an error for the form to not belong to this class. It returns DW\_DLV\_ERROR on error.

Never returns DW\_DLV\_NO\_ENTRY.

For DWARF2 and DWARF3, DW\_FORM\_data4 and DW\_FORM\_data8 are possibly class CONSTANT, and for DWARF4 and later they are definitely class CONSTANT.

### 5.6.11 dwarf\_formsdata()

```
int dwarf_formsdata(  
    Dwarf_Attribute attr,  
    Dwarf_Signed * return_svalue,  
    Dwarf_Error *error)
```

The function `dwarf_formsdata()` returns `DW_DLV_OK` and sets `*return_svalue` to the `Dwarf_Signed` value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the `CONSTANT` class. It is an error for the form to not belong to this class. If the size of the data attribute referenced is smaller than the size of the `Dwarf_Signed` type, its value is sign extended. It returns `DW_DLV_ERROR` on error.

Never returns `DW_DLV_NO_ENTRY`.

For DWARF2 and DWARF3, `DW_FORM_data4` and `DW_FORM_data8` are possibly class `CONSTANT`, and for DWARF4 and later they are definitely class `CONSTANT`.

### 5.6.12 dwarf\_formblock()

```
int dwarf_formblock(  
    Dwarf_Attribute attr,  
    Dwarf_Block ** return_block,  
    Dwarf_Error * error)
```

The function `dwarf_formblock()` returns `DW_DLV_OK` and sets `*return_block` to a pointer to a `Dwarf_Block` structure containing the value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the `BLOCK` class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of `dwarf_formblock()` should be freed using the allocation type `DW_DLA_BLOCK`, when no longer of interest (see `dwarf_dealloc()`). It returns `DW_DLV_ERROR` on error.

### 5.6.13 dwarf\_formstring()

```
int dwarf_formstring(  
    Dwarf_Attribute attr,  
    char ** return_string,  
    Dwarf_Error *error)
```

The function `dwarf_formstring()` returns `DW_DLV_OK` and sets `*return_string` to a pointer to a null-terminated string containing the value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the `STRING` class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of `dwarf_formstring()` should not be freed. The pointer points into existing DWARF memory and the pointer becomes stale/invalid after a call to `dwarf_finish`. `dwarf_formstring()` returns `DW_DLV_ERROR` on error.

### 5.6.14 dwarf\_formsig8()

```
int dwarf_formsig8(  
    Dwarf_Attribute attr,  
    Dwarf_Sig8 * return_sig8,  
    Dwarf_Error * error)
```

The function `dwarf_formsig8()` returns `DW_DLV_OK` and copies the 8 byte signature to a `Dwarf_Sig8` structure provided by the caller if the form of the attribute is of form `DW_FORM_ref_sig8` ( a member of the `REFERENCE` class). It is an error for the form to be anything but `DW_FORM_ref_sig8`. It returns `DW_DLV_ERROR` on error.

This form is used to refer to a type unit.

#### 5.6.15 dwarf\_formexprloc()

```
int dwarf_formexprloc(  
    Dwarf_Attribute attr,  
    Dwarf_Unsigned * return_exprlen,  
    Dwarf_Ptr * block_ptr,  
    Dwarf_Error * error)
```

The function `dwarf_formexprloc()` returns `DW_DLV_OK` and sets the two values thru the pointers to the length and bytes of the `DW_FORM_exprloc` entry if the form of the attribute is of form `DW_FORM_exprloc`. It is an error for the form to be anything but `DW_FORM_exprloc`. It returns `DW_DLV_ERROR` on error.

On success the value set through the `return_exprlen` pointer is the length of the location expression. On success the value set through the `block_ptr` pointer is a pointer to the bytes of the location expression itself.

#### 5.6.16 dwarf\_get\_form\_class()

```
enum Dwarf_Form_Class dwarf_get_form_class(  
    Dwarf_Half dwversion,  
    Dwarf_Half attrnum,  
    Dwarf_Half offset_size,  
    Dwarf_Half form)
```

The function is just for the convenience of libdwarf clients that might wish to categorize the `FORM` of a particular attribute. The DWARF specification divides `FORMs` into classes in Chapter 7 and this function figures out the correct class for a form.

The `dwversion` passed in shall be the dwarf version of the compilation unit involved (2 for DWARF2, 3 for DWARF3, 4 for DWARF 4). The `attrnum` passed in shall be the attribute number of the attribute involved (for example, `DW_AT_name` ). The `offset_size` passed in shall be the length of an offset in the current compilation unit (4 for 32bit dwarf or 8 for 64bit dwarf). The `form` passed in shall be the attribute form number. If form `DW_FORM_indirect` is passed in `DW_FORM_CLASS_UNKNOWN` will be returned as this form has no defined 'class'.

When it returns `DW_FORM_CLASS_UNKNOWN` the function is simply saying it could not determine the correct class given the arguments presented. Some user-defined attributes might have this problem.

The function `dwarf_get_version_of_die()` may be helpful in filling out arguments for a call to `dwarf_get_form_class()`.

#### 5.6.17 dwarf\_loclist\_n()

```
int dwarf_loclist_n(  
    Dwarf_Attribute attr,  
    Dwarf_Locdesc ***llbuf,  
    Dwarf_Signed *listlen,  
    Dwarf_Error *error)
```

The function `dwarf_loclist_n()` sets `*llbuf` to point to an array of `Dwarf_Locdesc` pointers corresponding to each of the location expressions in a location list, and sets `*listlen` to the number of elements in the array and returns `DW_DLV_OK` if the attribute is appropriate.

This is the preferred function for `Dwarf_Locdesc` as it is the interface allowing access to an entire loclist. (use of `dwarf_loclist_n()` is suggested as the better interface, though `dwarf_loclist()` is still supported.)

If the attribute is a reference to a location list (`DW_FORM_data4` or `DW_FORM_data8`) the location list entries are used to fill in all the fields of the `Dwarf_Locdesc(s)` returned.

If the attribute is a location description (`DW_FORM_block2` or `DW_FORM_block4`) then some of the `Dwarf_Locdesc` values of the single `Dwarf_Locdesc` record are set to 'sensible' but arbitrary values. Specifically, `ld_lopc` is set to 0 and `ld_hipec` is set to all-bits-on. And `*listlen` is set to 1.

If the attribute is a reference to a location expression (`DW_FORM_locexpr`) then some of the `Dwarf_Locdesc` values of the single `Dwarf_Locdesc` record are set to 'sensible' but arbitrary values. Specifically, `ld_lopc` is set to 0 and `ld_hipec` is set to all-bits-on. And `*listlen` is set to 1.

It returns `DW_DLV_ERROR` on error.

`dwarf_loclist_n()` works on `DW_AT_location`, `DW_AT_data_member_location`, `DW_AT_vtable_elem_location`, `DW_AT_string_length`, `DW_AT_use_location`, and `DW_AT_return_addr` attributes.

If the attribute is `DW_AT_data_member_location` the value may be of class `CONSTANT`. `dwarf_loclist_n()` is unable to read class `CONSTANT`, so you need to first determine the class using `dwarf_get_form_class()` and if it is class `CONSTANT` call `dwarf_formsdata()` or `dwarf_formudata()` to get the constant value (you may need to call both as DWARF4 does not define the signedness of the constant value).

Storage allocated by a successful call of `dwarf_loclist_n()` should be deallocated when no longer of interest (see `dwarf_dealloc()`). The block of `Dwarf_Loc` structs pointed to by the `ld_s` field of each `Dwarf_Locdesc` structure should be deallocated with the allocation type `DW_DLA_LOC_BLOCK`. and the `llbuf[]` space pointed to should be deallocated with allocation type `DW_DLA_LOCDISC`. This should be followed by deallocation of the `llbuf` using the allocation type `DW_DLA_LIST`.

```
Dwarf_Signed lcnt;
Dwarf_Locdesc **llbuf;
int lres;

lres = dwarf_loclist_n(someattr, &llbuf, &lcnt &error);
if (lres == DW_DLV_OK) {
    for (i = 0; i < lcnt; ++i) {
        /* use llbuf[i] */

        dwarf_dealloc(dbg, llbuf[i]->ld_s, DW_DLA_LOC_BLOCK);
        dwarf_dealloc(dbg, llbuf[i], DW_DLA_LOCDISC);
    }
    dwarf_dealloc(dbg, llbuf, DW_DLA_LIST);
}
```

## 5.6.18 dwarf\_loclist()

```
int dwarf_loclist(  
    Dwarf_Attribute attr,  
    Dwarf_Locdesc **llbuf,  
    Dwarf_Signed *listlen,  
    Dwarf_Error *error)
```

The function `dwarf_loclist()` sets `*llbuf` to point to a `Dwarf_Locdesc` pointer for the single location expression it can return. It sets `*listlen` to 1. and returns `DW_DLV_OK` if the attribute is appropriate.

It is less flexible than `dwarf_loclist_n()` in that `dwarf_loclist()` can handle a maximum of one location expression, not a full location list. If a location-list is present it returns only the first location-list entry location description. Use `dwarf_loclist_n()` instead.

It returns `DW_DLV_ERROR` on error. `dwarf_loclist()` works on `DW_AT_location`, `DW_AT_data_member_location`, `DW_AT_vtable_elem_location`, `DW_AT_string_length`, `DW_AT_use_location`, and `DW_AT_return_addr` attributes.

Storage allocated by a successful call of `dwarf_loclist()` should be deallocated when no longer of interest (see `dwarf_dealloc()`). The block of `Dwarf_Loc` structs pointed to by the `ld_s` field of each `Dwarf_Locdesc` structure should be deallocated with the allocation type `DW_DLA_LOC_BLOCK`. This should be followed by deallocation of the `llbuf` using the allocation type `DW_DLA_LOCDISC`.

```
Dwarf_Signed lcnt;  
Dwarf_Locdesc *llbuf;  
int lres;  
  
lres = dwarf_loclist(someattr, &llbuf,&lcnt,&error);  
if (lres == DW_DLV_OK) {  
    /* lcnt is always 1, (and has always been 1) */ */  
  
    /* Use llbuf here. */  
  
    dwarf_dealloc(dbg, llbuf->ld_s, DW_DLA_LOC_BLOCK);  
    dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDISC);  
    /* Earlier version.  
    *     for (i = 0; i < lcnt; ++i) {  
    *         /* use llbuf[i] */  
    *  
    *         /* Deallocate Dwarf_Loc block of llbuf[i] */  
    *         dwarf_dealloc(dbg, llbuf[i].ld_s, DW_DLA_LOC_BLOCK);  
    *     }  
    *     dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDISC);  
    */  
}
```

### 5.6.19 dwarf\_loclist\_from\_expr()



```
int dwarf_loclist_from_expr(  
    Dwarf_Ptr bytes_in,  
    Dwarf_Unsigned bytes_len,  
    Dwarf_Locdesc **llbuf,  
    Dwarf_Signed *listlen,  
    Dwarf_Error *error)
```

Use `dwarf_loclist_from_expr_b()` instead. This function is obsolete.

The function `dwarf_loclist_from_expr()` sets `*llbuf` to point to a `Dwarf_Locdesc` pointer for the single location expression which is pointed to by `*bytes_in` (whose length is `*bytes_len`). It sets `*listlen` to 1. and returns `DW_DLV_OK` if decoding is successful. Some sources of bytes of expressions are dwarf expressions in frame operations like `DW_CFA_def_cfa_expression`, `DW_CFA_expression`, and `DW_CFA_val_expression`.

Any `address_size` data in the location expression is assumed to be the same size as the default `address_size` for the object being read (normally 4 or 8).

It returns `DW_DLV_ERROR` on error.

Storage allocated by a successful call of `dwarf_loclist_from_expr()` should be deallocated when no longer of interest (see `dwarf_dealloc()`). The block of `Dwarf_Loc` structs pointed to by the `ld_s` field of each `Dwarf_Locdesc` structure should be deallocated with the allocation type `DW_DLA_LOC_BLOCK`. This should be followed by deallocation of the `llbuf` using the allocation type `DW_DLA_LOCDISC`.

```
Dwarf_Signed lcnt;  
Dwarf_Locdesc *llbuf;  
int lres;  
/* Example with an empty buffer here. */  
Dwarf_Ptr data = "";  
Dwarf_Unsigned len = 0;  
  
lres = dwarf_loclist_from_expr(data, len, &llbuf, &lcnt, &error);  
if (lres == DW_DLV_OK) {  
    /* lcmt is always 1 */  
  
    /* Use llbuf here.*/  
  
    dwarf_dealloc(dbg, llbuf->ld_s, DW_DLA_LOC_BLOCK);  
    dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDISC);  
}
```

### 5.6.20 dwarf\_loclist\_from\_expr\_b()

```
int dwarf_loclist_from_expr_a(  
    Dwarf_Ptr bytes_in,  
    Dwarf_Unsigned bytes_len,  
    Dwarf_Half addr_size,  
    Dwarf_Half offset_size,  
    Dwarf_Half version_stamp,  
    Dwarf_Locdesc **llbuf,  
    Dwarf_Signed *listlen,  
    Dwarf_Error *error)
```

The function `dwarf_loclist_from_expr_b()` is identical to `dwarf_loclist_from_expr_a()` in every way except that the caller passes an additional argument `version_stamp` containing the version stamp (2 for DWARF2, etc) of the CU using this location

expression and an additional argument of the offset size of the CU using this location expression. The DW\_OP\_GNU\_implicit\_pointer operation requires this version and offset information to be correctly processed.

The `addr_size` argument (from 27April2009) is needed to correctly interpret frame information as different compilation units can have different address sizes. DWARF4 adds `address_size` to the CIE header.

### 5.6.21 `dwarf_loclist_from_expr_a()`

```
int dwarf_loclist_from_expr_a(  
    Dwarf_Ptr bytes_in,  
    Dwarf_Unsigned bytes_len,  
    Dwarf_Half addr_size,  
    Dwarf_Locdesc **llbuf,  
    Dwarf_Signed *listlen,  
    Dwarf_Error *error)
```

Use `dwarf_loclist_from_expr_b()` instead. This function is obsolete.

The function `dwarf_loclist_from_expr_a()` is identical to `dwarf_loclist_from_expr()` in every way except that the caller passes the additional argument `addr_size` containing the address size (normally 4 or 8) applying this location expression.

The `addr_size` argument (added 27April2009) is needed to correctly interpret frame information as different compilation units can have different address sizes. DWARF4 adds `address_size` to the CIE header.

## 5.7 Line Number Operations

These functions are concerned with accessing line number entries, mapping debugging information entry objects to their corresponding source lines, and providing a mechanism for obtaining information about line number entries. Although, the interface talks of "lines" what is really meant is "statements". In case there is more than one statement on the same line, there will be at least one descriptor per statement, all with the same line number. If column number is also being represented they will have the column numbers of the start of the statements also represented.

There can also be more than one `Dwarf_Line` per statement. For example, if a file is preprocessed by a language translator, this could result in translator output showing 2 or more sets of line numbers per translated line of output.

### 5.7.1 Get A Set of Lines

The function returns information about every source line for a particular compilation-unit. The compilation-unit is specified by the corresponding die.

#### 5.7.1.1 `dwarf_srclines()`

```
int dwarf_srclines(  
    Dwarf_Die die,  
    Dwarf_Line **linebuf,  
    Dwarf_Signed *linecount,  
    Dwarf_Error *error)
```

The function `dwarf_srclines()` places all line number descriptors for a single compilation unit into a single block, sets `*linebuf` to point to that block, sets `*linecount` to the number of descriptors in this block and returns `DW_DLV_OK`. The compilation-unit is indicated by the given `die` which must be a compilation-unit die. It returns `DW_DLV_ERROR` on error. On successful return, line number information should be freed using `dwarf_srclines_dealloc()` when no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Line *linebuf;
int sres;

sres = dwarf_srclines(somedie, &linebuf,&cnt, &error);
if (sres == DW_DLV_OK) {
    for (i = 0; i < cnt; ++i) {
        /* use linebuf[i] */
    }
    dwarf_srclines_dealloc(dbg, linebuf, cnt);
}
```

The following dealloc code (the only documented method before July 2005) still works, but does not completely free all data allocated. The `dwarf_srclines_dealloc()` routine was created to fix the problem of incomplete deallocation.

```
Dwarf_Signed cnt;
Dwarf_Line *linebuf;
int sres;

sres = dwarf_srclines(somedie, &linebuf,&cnt, &error);
if (sres == DW_DLV_OK) {
    for (i = 0; i < cnt; ++i) {
        /* use linebuf[i] */
        dwarf_dealloc(dbg, linebuf[i], DW_DLA_LINE);
    }
    dwarf_dealloc(dbg, linebuf, DW_DLA_LIST);
}
```

## 5.7.2 Get the set of Source File Names

The function returns the names of the source files that have contributed to the compilation-unit represented by the given DIE. Only the source files named in the statement program prologue are returned.

```
int dwarf_srcfiles(
    Dwarf_Die die,
    char ***srcfiles,
    Dwarf_Signed *srccount,
    Dwarf_Error *error)
```

When it succeeds `dwarf_srcfiles()` returns `DW_DLV_OK` and puts the number of source files named in the statement program prologue indicated by the given die into `*srccount`. Source files defined in the statement program are ignored. The given die should have the tag `DW_TAG_compile_unit`, `DW_TAG_partial_unit`, or `DW_TAG_type_unit`. The location pointed to by `srcfiles` is set to point to a list of pointers to null-terminated strings that name the source files. On a successful return from this function, each of the strings returned should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_STRING` when no longer of interest. This should be followed by free-ing the list using `dwarf_dealloc()` with the allocation type `DW_DLA_LIST`. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if there is no corresponding statement program (i.e., if there is no line information).

```
Dwarf_Signed cnt;
char **srcfiles;
int res;

res = dwarf_srcfiles(somedie, &srcfiles,&cnt &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use srcfiles[i] */
        dwarf_dealloc(dbg, srcfiles[i], DW_DLA_STRING);
    }
    dwarf_dealloc(dbg, srcfiles, DW_DLA_LIST);
}
```

### 5.7.3 Get information about a Single Table Line

The following functions can be used on the Dwarf\_Line descriptors returned by dwarf\_srclines() to obtain information about the source lines.

#### 5.7.3.1 dwarf\_linebeginstatement()

```
int dwarf_linebeginstatement(
    Dwarf_Line line,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

The function dwarf\_linebeginstatement() returns DW\_DLV\_OK and sets \*return\_bool to *non-zero* (if line represents a line number entry that is marked as beginning a statement). or *zero* (if line represents a line number entry that is not marked as beginning a statement). It returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.7.3.2 dwarf\_lineendsequence()

```
int dwarf_lineendsequence(
    Dwarf_Line line,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

The function dwarf\_lineendsequence() returns DW\_DLV\_OK and sets \*return\_bool *non-zero* (in which case line represents a line number entry that is marked as ending a text sequence) or *zero* (in which case line represents a line number entry that is not marked as ending a text sequence). A line number entry that is marked as ending a text sequence is an entry with an address one beyond the highest address used by the current sequence of line table entries (that is, the table entry is a DW\_LNE\_end\_sequence entry (see the DWARF specification)).

The function dwarf\_lineendsequence() returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.7.3.3 dwarf\_lineno()

```
int dwarf_lineno(
    Dwarf_Line line,
    Dwarf_Unsigned * returned_lineno,
    Dwarf_Error * error)
```

The function dwarf\_lineno() returns DW\_DLV\_OK and sets \*return\_lineno to the source statement line number corresponding to the descriptor line. It returns DW\_DLV\_ERROR on error. It

never returns DW\_DLV\_NO\_ENTRY.

#### 5.7.3.4 dwarf\_line\_srcfileno()

```
int dwarf_line_srcfileno(  
    Dwarf_Line      line,  
    Dwarf_Unsigned * returned_fileno,  
    Dwarf_Error     * error)
```

The function `dwarf_line_srcfileno()` returns DW\_DLV\_OK and sets `*returned_fileno` to the source statement line number corresponding to the descriptor file number. When the number returned through `*returned_fileno` is zero it means the file name is unknown (see the DWARF2/3 line table specification). When the number returned through `*returned_fileno` is non-zero it is a file number: subtract 1 from this file number to get an index into the array of strings returned by `dwarf_srcfiles()` (verify the resulting index is in range for the array of strings before indexing into the array of strings). The file number may exceed the size of the array of strings returned by `dwarf_srcfiles()` because `dwarf_srcfiles()` does not return files names defined with the DW\_DLE\_define\_file operator. The function `dwarf_line_srcfileno()` returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.7.3.5 dwarf\_lineaddr()

```
int dwarf_lineaddr(  
    Dwarf_Line line,  
    Dwarf_Addr *return_lineaddr,  
    Dwarf_Error *error)
```

The function `dwarf_lineaddr()` returns DW\_DLV\_OK and sets `*return_lineaddr` to the address associated with the descriptor line. It returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.7.3.6 dwarf\_lineoff()

```
int dwarf_lineoff(  
    Dwarf_Line line,  
    Dwarf_Signed * return_lineoff,  
    Dwarf_Error *error)
```

The function `dwarf_lineoff()` returns DW\_DLV\_OK and sets `*return_lineoff` to the column number at which the statement represented by line begins.

It sets `return_lineoff` to zero if the column number of the statement is not represented (meaning the producer library call was given zero as the column number). Zero is the correct value meaning "left edge" as defined in the DWARF2/3/4 specification (section 6.2.2).

Before December 2011 zero was not returned through the `return_lineoff` pointer, -1 was returned through the pointer. The reason for this oddity is unclear, lost in history. But there is no good reason for -1.

The type of `return_lineoff` is a pointer-to-signed, but there is no good reason for the value to be signed, the DWARF specification does not deal with negative column numbers. However, changing the declaration would cause compilation errors for little benefit, so the pointer-to-signed is left unchanged.

On error it returns DW\_DLV\_ERROR. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.7.3.7 dwarf\_linesrc()

```
int dwarf_linesrc(  
    Dwarf_Line line,  
    char ** return_linesrc,  
    Dwarf_Error *error)
```

The function `dwarf_linesrc()` returns `DW_DLV_OK` and sets `*return_linesrc` to a pointer to a null-terminated string of characters that represents the name of the source-file where line occurs. It returns `DW_DLV_ERROR` on error.

If the applicable file name in the line table Statement Program Prolog does not start with a `'/'` character the string in `DW_AT_comp_dir` (if applicable and present) or the applicable directory name from the line Statement Program Prolog is prepended to the file name in the line table Statement Program Prolog to make a full path.

The storage pointed to by a successful return of `dwarf_linesrc()` should be freed using `dwarf_dealloc()` with the allocation type `DW_DLA_STRING` when no longer of interest. It never returns `DW_DLV_NO_ENTRY`.

#### 5.7.3.8 dwarf\_lineblock()

```
int dwarf_lineblock(  
    Dwarf_Line line,  
    Dwarf_Bool *return_bool,  
    Dwarf_Error *error)
```

The function `dwarf_lineblock()` returns `DW_DLV_OK` and sets `*return_linesrc` to non-zero (i.e. true) if the line is marked as beginning a basic block) or zero (i.e. false) (if the line is marked as not beginning a basic block). It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.7.3.9 dwarf\_line\_is\_addr\_set()

```
int dwarf_line_is_addr_set(  
    Dwarf_Line line,  
    Dwarf_Bool *return_bool,  
    Dwarf_Error *error)
```

The function `dwarf_line_is_addr_set()` returns `DW_DLV_OK` and sets `*return_bool` to non-zero (i.e. true) if the line is marked as being a `DW_LNE_set_address` operation) or zero (i.e. false) (if the line is marked as not being a `DW_LNE_set_address` operation). It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

This is intended to allow consumers to do a more useful job printing and analyzing DWARF data, it is not strictly necessary.

#### 5.7.3.10 dwarf\_prologue\_end\_etc()

```
int dwarf_prologue_end_etc(Dwarf_Line line,  
    Dwarf_Bool * prologue_end,  
    Dwarf_Bool * epilogue_begin,  
    Dwarf_Unsigned * isa,  
    Dwarf_Unsigned * discriminator,  
    Dwarf_Error * error)
```

The function `dwarf_prologue_end_etc()` returns `DW_DLV_OK` and sets the returned fields to values currently set. While it is pretty safe to assume that the `isa` and `discriminator` values returned are very small integers, there is no restriction in the standard. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

This function is new in December 2011.

## 5.8 Global Name Space Operations

These operations operate on the .debug\_pubnames section of the debugging information.

## 5.9 Global Name Space Operations

These operations operate on the .debug\_pubnames section of the debugging information.

### 5.9.1 Debugger Interface Operations

#### 5.9.1.1 dwarf\_get\_globals()

```
int dwarf_get_globals(  
    Dwarf_Debug dbg,  
    Dwarf_Global **globals,  
    Dwarf_Signed * return_count,  
    Dwarf_Error *error)
```

The function `dwarf_get_globals()` returns `DW_DLV_OK` and sets `*return_count` to the count of pubnames represented in the section containing pubnames i.e. `.debug_pubnames`. It also stores at `*globals`, a pointer to a list of `Dwarf_Global` descriptors, one for each of the pubnames in the `.debug_pubnames` section. The returned results are for the entire section. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_pubnames` section does not exist.

On a successful return from `dwarf_get_globals()`, the `Dwarf_Global` descriptors should be freed using `dwarf_globals_dealloc()`. `dwarf_globals_dealloc()` is new as of July 15, 2005 and is the preferred approach to freeing this memory..

Global names refer exclusively to names and offsets in the `.debug_info` section. See section 6.1.1 "Lookup by Name" in the dwarf standard.

```
Dwarf_Signed cnt;  
Dwarf_Global *globs;  
int res;  
  
res = dwarf_get_globals(dbg, &globs,&cnt, &error);  
if (res == DW_DLV_OK) {  
  
    for (i = 0; i < cnt; ++i) {  
        /* use globs[i] */  
    }  
    dwarf_globals_dealloc(dbg, globs, cnt);  
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_globals()`, the `Dwarf_Global` descriptors should be individually freed using `dwarf_dealloc()` with the allocation

type DW\_DLA\_GLOBAL\_CONTEXT, (or DW\_DLA\_GLOBAL, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type DW\_DLA\_LIST when the descriptors are no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Global *globs;
int res;

res = dwarf_get_globals(dbg, &globs, &cnt, &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use globs[i] */
        dwarf_dealloc(dbg, globs[i], DW_DLA_GLOBAL_CONTEXT);
    }
    dwarf_dealloc(dbg, globs, DW_DLA_LIST);
}
```

#### 5.9.1.2 dwarf\_globname()

```
int dwarf_globname(
    Dwarf_Global global,
    char **      return_name,
    Dwarf_Error *error)
```

The function `dwarf_globname()` returns DW\_DLV\_OK and sets `*return_name` to a pointer to a null-terminated string that names the pubname represented by the Dwarf\_Global descriptor, `global`. It returns DW\_DLV\_ERROR on error. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type DW\_DLA\_STRING when no longer of interest. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.9.1.3 dwarf\_global\_die\_offset()

```
int dwarf_global_die_offset(
    Dwarf_Global global,
    Dwarf_Off    *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_global_die_offset()` returns DW\_DLV\_OK and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the pubname that is described by the Dwarf\_Global descriptor, `glob`. It returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY.

#### 5.9.1.4 dwarf\_global\_cu\_offset()

```
int dwarf_global_cu_offset(
    Dwarf_Global global,
    Dwarf_Off    *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_global_cu_offset()` returns DW\_DLV\_OK and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the pubname described by the Dwarf\_Global descriptor, `global`. It returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY.



#### 5.9.1.5 dwarf\_get\_cu\_die\_offset\_given\_cu\_header\_offset()

```
int dwarf_get_cu_die_offset_given_cu_header_offset_b(  
    Dwarf_Debug dbg,  
    Dwarf_Off   in_cu_header_offset,  
    Dwarf_Bool  is_info,  
    Dwarf_Off * out_cu_die_offset,  
    Dwarf_Error *error)
```

The function `dwarf_get_cu_die_offset_given_cu_header_offset()` returns `DW_DLV_OK` and sets `*out_cu_die_offset` to the offset of the compilation-unit DIE given the offset `in_cu_header_offset` of a compilation-unit header. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

If `is_info` is non-zero the `in_cu_header_offset` must refer to a `.debug_info` section offset. If `is_info` zero the `in_cu_header_offset` must refer to a `.debug_types` section offset. Chaos may result if the `is_info` flag is incorrect.

This effectively turns a compilation-unit-header offset into a compilation-unit DIE offset (by adding the size of the applicable CU header). This function is also sometimes useful with the `dwarf_weak_cu_offset()`, `dwarf_func_cu_offset()`, `dwarf_type_cu_offset()`, and `int dwarf_var_cu_offset()` functions, though for those functions the data is only in `.debug_info` by definition.

#### 5.9.1.6 dwarf\_get\_cu\_die\_offset\_given\_cu\_header\_offset()

```
int dwarf_get_cu_die_offset_given_cu_header_offset(  
    Dwarf_Debug dbg,  
    Dwarf_Off   in_cu_header_offset,  
    Dwarf_Off * out_cu_die_offset,  
    Dwarf_Error *error)
```

This function is superseded by `dwarf_get_cu_die_offset_given_cu_header_offset_b()`, a function which is still supported though it refers only to the `.debug_info` section.

`dwarf_get_cu_die_offset_given_cu_header_offset()` added Rev 1.45, June, 2001.

This function is declared as 'optional' in `libdwarf.h` on IRIX systems so the `_MIPS_SYMBOL_PRESENT` predicate may be used at run time to determine if the version of `libdwarf` linked into an application has this function.

#### 5.9.1.7 dwarf\_global\_name\_offsets()

```
int dwarf_global_name_offsets(  
    Dwarf_Global global,  
    char **return_name,  
    Dwarf_Off *die_offset,  
    Dwarf_Off *cu_offset,  
    Dwarf_Error *error)
```

The function `dwarf_global_name_offsets()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that gives the name of the pubname described by the `Dwarf_Global` descriptor `global`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the pubname, and the DIE representing the compilation-unit containing the pubname, respectively. On a successful return from `dwarf_global_name_offsets()` the storage pointed to by `return_name`

should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

## 5.10 DWARF3 Type Names Operations

Section ".debug\_pubtypes" is new in DWARF3.

These functions operate on the .debug\_pubtypes section of the debugging information. The .debug\_pubtypes section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

### 5.10.1 Debugger Interface Operations

#### 5.10.1.1 dwarf\_get\_pubtypes()

```
int dwarf_get_pubtypes(
    Dwarf_Debug dbg,
    Dwarf_Type **types,
    Dwarf_Signed *typecount,
    Dwarf_Error *error)
```

The function `dwarf_get_pubtypes()` returns `DW_DLV_OK` and sets `*typecount` to the count of user-defined type names represented in the section containing user-defined type names, i.e. .debug\_pubtypes. It also stores at `*types`, a pointer to a list of `Dwarf_Type` descriptors, one for each of the user-defined type names in the .debug\_pubtypes section. The returned results are for the entire section. It returns `DW_DLV_NOCOUNT` on error. It returns `DW_DLV_NO_ENTRY` if the .debug\_pubtypes section does not exist.

On a successful return from `dwarf_get_pubtypes()`, the `Dwarf_Type` descriptors should be freed using `dwarf_types_dealloc()`. `dwarf_types_dealloc()` is used for both `dwarf_get_pubtypes()` and `dwarf_get_types()` as the data types are the same.

Global type names refer exclusively to names and offsets in the .debug\_info section. See section 6.1.1 "Lookup by Name" in the dwarf standard.

```
Dwarf_Signed cnt;
Dwarf_Type *types;
int res;

res = dwarf_get_pubtypes(dbg, &types, &cnt, &error);
if (res == DW_DLV_OK) {
    for (i = 0; i < cnt; ++i) {
        /* use types[i] */
    }
    dwarf_types_dealloc(dbg, types, cnt);
}
```

#### 5.10.1.2 dwarf\_pubtypename()

```
int dwarf_pubtypename(  
    Dwarf_Type type,  
    char      **return_name,  
    Dwarf_Error *error)
```

The function `dwarf_pubtypename()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the user-defined type represented by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

#### 5.10.1.3 dwarf\_pubtype\_die\_offset()

```
int dwarf_pubtype_die_offset(  
    Dwarf_Type type,  
    Dwarf_Off *return_offset,  
    Dwarf_Error *error)
```

The function `dwarf_pubtype_die_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the user-defined type that is described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.10.1.4 dwarf\_pubtype\_cu\_offset()

```
int dwarf_pubtype_cu_offset(  
    Dwarf_Type type,  
    Dwarf_Off *return_offset,  
    Dwarf_Error *error)
```

The function `dwarf_pubtype_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.10.1.5 dwarf\_pubtype\_name\_offsets()

```
int dwarf_pubtype_name_offsets(  
    Dwarf_Type type,  
    char      ** returned_name,  
    Dwarf_Off * die_offset,  
    Dwarf_Off * cu_offset,  
    Dwarf_Error *error)
```

The function `dwarf_pubtype_name_offsets()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that gives the name of the user-defined type described by the `Dwarf_Type` descriptor `type`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_pubtype_name_offsets()` the storage pointed to by `returned_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

## 5.11 User Defined Static Variable Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These functions operate on the `.debug_varnames` section of the debugging information. The `.debug_varnames` section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

## 5.12 Weak Name Space Operations

These operations operate on the `.debug_weaknames` section of the debugging information.

These operations are SGI specific, not part of standard DWARF.

### 5.12.1 Debugger Interface Operations

#### 5.12.1.1 `dwarf_get_weak`s()

```
int dwarf_get_weak(
    Dwarf_Debug dbg,
    Dwarf_Weak **weak,
    Dwarf_Signed *weak_count,
    Dwarf_Error *error)
```

The function `dwarf_get_weak()` returns `DW_DLV_OK` and sets `*weak_count` to the count of weak names represented in the section containing weak names i.e. `.debug_weaknames`. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the section does not exist. It also stores in `*weak`, a pointer to a list of `Dwarf_Weak` descriptors, one for each of the weak names in the `.debug_weaknames` section. The returned results are for the entire section.

On a successful return from this function, the `Dwarf_Weak` descriptors should be freed using `dwarf_weak_dealloc()` when the data is no longer of interest. `dwarf_weak_dealloc()` is new as of July 15, 2005.

```
Dwarf_Signed cnt;
Dwarf_Weak *weak;
int res;

res = dwarf_get_weak(dbg, &weak, &cnt, &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use weak[i] */
    }
    dwarf_weak_dealloc(dbg, weak, cnt);
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach

still works as well as it ever did. On a successful return from `dwarf_get_weak()` the `Dwarf_Weak` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_WEAK_CONTEXT`, (or `DW_DLA_WEAK`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Weak *weak;
int res;

res = dwarf_get_weak(dbg, &weak, &cnt, &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use weak[i] */
        dwarf_dealloc(dbg, weak[i], DW_DLA_WEAK_CONTEXT);
    }
    dwarf_dealloc(dbg, weak, DW_DLA_LIST);
}
```

#### 5.12.1.2 dwarf\_weakname()

```
int dwarf_weakname(
    Dwarf_Weak weak,
    char ** return_name,
    Dwarf_Error *error)
```

The function `dwarf_weakname()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the weak name represented by the `Dwarf_Weak` descriptor, `weak`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

```
int dwarf_weak_die_offset(
    Dwarf_Weak weak,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_weak_die_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the weak name that is described by the `Dwarf_Weak` descriptor, `weak`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.12.1.3 dwarf\_weak\_cu\_offset()

```
int dwarf_weak_cu_offset(
    Dwarf_Weak weak,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_weak_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the weak name described by the `Dwarf_Weak` descriptor, `weak`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.12.1.4 dwarf\_weak\_name\_offsets()

```
int dwarf_weak_name_offsets(  
    Dwarf_Weak weak,  
    char ** weak_name,  
    Dwarf_Off *die_offset,  
    Dwarf_Off *cu_offset,  
    Dwarf_Error *error)
```

The function `dwarf_weak_name_offsets()` returns `DW_DLV_OK` and sets `*weak_name` to a pointer to a null-terminated string that gives the name of the weak name described by the `Dwarf_Weak` descriptor `weak`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the weakname, and the DIE representing the compilation-unit containing the weakname, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_weak_name_offsets()` the storage pointed to by `weak_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

### 5.13 Static Function Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These function operate on the `.debug_funcnames` section of the debugging information. The `.debug_funcnames` section contains the names of static functions defined in the object, the offsets of the DIEs that represent the definitions of the corresponding functions, and the offsets of the start of the compilation-units that contain the definitions of those functions.

#### 5.13.1 Debugger Interface Operations

##### 5.13.1.1 dwarf\_get\_funcs()

```
int dwarf_get_funcs(  
    Dwarf_Debug dbg,  
    Dwarf_Func **funcs,  
    Dwarf_Signed *func_count,  
    Dwarf_Error *error)
```

The function `dwarf_get_funcs()` returns `DW_DLV_OK` and sets `*func_count` to the count of static function names represented in the section containing static function names, i.e. `.debug_funcnames`. It also stores, at `*funcs`, a pointer to a list of `Dwarf_Func` descriptors, one for each of the static functions in the `.debug_funcnames` section. The returned results are for the entire section. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_funcnames` section does not exist.

On a successful return from `dwarf_get_funcs()`, the `Dwarf_Func` descriptors should be freed using `dwarf_funcs_dealloc()`. `dwarf_funcs_dealloc()` is new as of July 15, 2005.

```
Dwarf_Signed cnt;
Dwarf_Func *funcs;
int fres;

fres = dwarf_get_funcs(dbg, &funcs, &cnt, &error);
if (fres == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use funcs[i] */
    }
    dwarf_funcs_dealloc(dbg, funcs, cnt);
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_funcs()`, the `Dwarf_Func` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_FUNC_CONTEXT`, (or `DW_DLA_FUNC`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Func *funcs;
int fres;

fres = dwarf_get_funcs(dbg, &funcs, &error);
if (fres == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use funcs[i] */
        dwarf_dealloc(dbg, funcs[i], DW_DLA_FUNC_CONTEXT);
    }
    dwarf_dealloc(dbg, funcs, DW_DLA_LIST);
}
```

#### 5.13.1.2 dwarf\_funcname()

```
int dwarf_funcname(
    Dwarf_Func func,
    char **    return_name,
    Dwarf_Error *error)
```

The function `dwarf_funcname()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the static function represented by the `Dwarf_Func` descriptor, `func`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

#### 5.13.1.3 dwarf\_func\_die\_offset()

```
int dwarf_func_die_offset(  
    Dwarf_Func func,  
    Dwarf_Off *return_offset,  
    Dwarf_Error *error)
```

The function `dwarf_func_die_offset()`, returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the static function that is described by the `Dwarf_Func` descriptor, `func`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.13.1.4 dwarf\_func\_cu\_offset()

```
int dwarf_func_cu_offset(  
    Dwarf_Func func,  
    Dwarf_Off *return_offset,  
    Dwarf_Error *error)
```

The function `dwarf_func_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the static function described by the `Dwarf_Func` descriptor, `func`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.13.1.5 dwarf\_func\_name\_offsets()

```
int dwarf_func_name_offsets(  
    Dwarf_Func func,  
    char **func_name,  
    Dwarf_Off *die_offset,  
    Dwarf_Off *cu_offset,  
    Dwarf_Error *error)
```

The function `dwarf_func_name_offsets()` returns `DW_DLV_OK` and sets `*func_name` to a pointer to a null-terminated string that gives the name of the static function described by the `Dwarf_Func` descriptor `func`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the static function, and the DIE representing the compilation-unit containing the static function, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_func_name_offsets()` the storage pointed to by `func_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

## 5.14 User Defined Type Names Operations

Section "debug\_typednames" is SGI specific and is not part of standard DWARF version 2. (However, an identical section is part of DWARF version 3 named ".debug\_pubtypes", see `dwarf_get_pubtypes()` above.)

These functions operate on the `.debug_typednames` section of the debugging information. The `.debug_typednames` section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

### 5.14.1 Debugger Interface Operations



#### 5.14.1.1 dwarf\_get\_types()

```
int dwarf_get_types(  
    Dwarf_Debug dbg,  
    Dwarf_Type **types,  
    Dwarf_Signed *typecount,  
    Dwarf_Error *error)
```

The function `dwarf_get_types()` returns `DW_DLV_OK` and sets `*typecount` to the count of user-defined type names represented in the section containing user-defined type names, i.e. `.debug_typenames`. It also stores at `*types`, a pointer to a list of `Dwarf_Type` descriptors, one for each of the user-defined type names in the `.debug_typenames` section. The returned results are for the entire section. It returns `DW_DLV_NOCOUNT` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_typenames` section does not exist.

On a successful return from `dwarf_get_types()`, the `Dwarf_Type` descriptors should be freed using `dwarf_types_dealloc()`. `dwarf_types_dealloc()` is new as of July 15, 2005 and frees all memory allocated by `dwarf_get_types()`.

```
Dwarf_Signed cnt;  
Dwarf_Type *types;  
int res;  
  
res = dwarf_get_types(dbg, &types, &cnt, &error);  
if (res == DW_DLV_OK) {  
    for (i = 0; i < cnt; ++i) {  
        /* use types[i] */  
    }  
    dwarf_types_dealloc(dbg, types, cnt);  
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_types()`, the `Dwarf_Type` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_TYPENAME_CONTEXT`, (or `DW_DLA_TYPENAME`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Type *types;
int res;

res = dwarf_get_types(dbg, &types,&cnt, &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use types[i] */
        dwarf_dealloc(dbg, types[i], DW_DLA_TYPENAME_CONTEXT);
    }
    dwarf_dealloc(dbg, types, DW_DLA_LIST);
}
```

#### 5.14.1.2 dwarf\_typename()

```
int dwarf_typename(
    Dwarf_Type type,
    char **return_name,
    Dwarf_Error *error)
```

The function `dwarf_typename()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the user-defined type represented by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

#### 5.14.1.3 dwarf\_type\_die\_offset()

```
int dwarf_type_die_offset(
    Dwarf_Type type,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_type_die_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the user-defined type that is described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.14.1.4 dwarf\_type\_cu\_offset()

```
int dwarf_type_cu_offset(
    Dwarf_Type type,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_type_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.14.1.5 dwarf\_type\_name\_offsets()

```
int dwarf_type_name_offsets(  
    Dwarf_Type    type,  
    char          ** returned_name,  
    Dwarf_Off *   die_offset,  
    Dwarf_Off *   cu_offset,  
    Dwarf_Error *error)
```

The function `dwarf_type_name_offsets()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that gives the name of the user-defined type described by the `Dwarf_Type` descriptor `type`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_type_name_offsets()` the storage pointed to by `returned_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

## 5.15 User Defined Static Variable Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These functions operate on the `.debug_varnames` section of the debugging information. The `.debug_varnames` section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

### 5.15.1 Debugger Interface Operations

#### 5.15.1.1 `dwarf_get_vars()`

```
int dwarf_get_vars(  
    Dwarf_Debug dbg,  
    Dwarf_Var **vars,  
    Dwarf_Signed *var_count,  
    Dwarf_Error *error)
```

The function `dwarf_get_vars()` returns `DW_DLV_OK` and sets `*var_count` to the count of file-scope static variable names represented in the section containing file-scope static variable names, i.e. `.debug_varnames`. It also stores, at `*vars`, a pointer to a list of `Dwarf_Var` descriptors, one for each of the file-scope static variable names in the `.debug_varnames` section. The returned results are for the entire section. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_varnames` section does not exist.

The following is new as of July 15, 2005. On a successful return from `dwarf_get_vars()`, the `Dwarf_Var` descriptors should be freed using `dwarf_vars_dealloc()`.

```
Dwarf_Signed cnt;
Dwarf_Var *vars;
int res;

res = dwarf_get_vars(dbg, &vars,&cnt &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use vars[i] */
    }
    dwarf_vars_dealloc(dbg, vars, cnt);
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_vars()`, the `Dwarf_Var` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_VAR_CONTEXT`, (or `DW_DLA_VAR`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Var *vars;
int res;

res = dwarf_get_vars(dbg, &vars,&cnt &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use vars[i] */
        dwarf_dealloc(dbg, vars[i], DW_DLA_VAR_CONTEXT);
    }
    dwarf_dealloc(dbg, vars, DW_DLA_LIST);
}
```

#### 5.15.1.2 dwarf\_varname()

```
int dwarf_varname(
    Dwarf_Var var,
    char **    returned_name,
    Dwarf_Error *error)
```

The function `dwarf_varname()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that names the file-scope static variable represented by the `Dwarf_Var` descriptor, `var`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

#### 5.15.1.3 dwarf\_var\_die\_offset()

```
int dwarf_var_die_offset(  
    Dwarf_Var    var,  
    Dwarf_Off    *returned_offset,  
    Dwarf_Error  *error)
```

The function `dwarf_var_die_offset()` returns `DW_DLV_OK` and sets `*returned_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the file-scope static variable that is described by the `Dwarf_Var` descriptor, `var`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.15.1.4 dwarf\_var\_cu\_offset()

```
int dwarf_var_cu_offset(  
    Dwarf_Var var,  
    Dwarf_Off *returned_offset,  
    Dwarf_Error *error)
```

The function `dwarf_var_cu_offset()` returns `DW_DLV_OK` and sets `*returned_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the file-scope static variable described by the `Dwarf_Var` descriptor, `var`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

#### 5.15.1.5 dwarf\_var\_name\_offsets()

```
int dwarf_var_name_offsets(  
    Dwarf_Var var,  
    char      **returned_name,  
    Dwarf_Off *die_offset,  
    Dwarf_Off *cu_offset,  
    Dwarf_Error *error)
```

The function `dwarf_var_name_offsets()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that gives the name of the file-scope static variable described by the `Dwarf_Var` descriptor `var`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the file-scope static variable, and the DIE representing the compilation-unit containing the file-scope static variable, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_var_name_offsets()` the storage pointed to by `returned_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

## 5.16 Macro Information Operations

### 5.16.1 General Macro Operations

#### 5.16.1.1 dwarf\_find\_macro\_value\_start()

```
char *dwarf_find_macro_value_start(char * macro_string);
```

Given a macro string in the standard form defined in the DWARF document ("name <space> value" or "name(args)<space>value") this returns a pointer to the first byte of the macro value. It does not alter the string pointed to by `macro_string` or copy the string: it returns a pointer into the string whose address was passed in.

### 5.16.2 Debugger Interface Macro Operations

Macro information is accessed from the `.debug_info` section via the `DW_AT_macro_info` attribute (whose value is an offset into `.debug_macinfo`).

No Functions yet defined.

### 5.16.3 Low Level Macro Information Operations

#### 5.16.3.1 dwarf\_get\_macro\_details()

```
int dwarf_get_macro_details(Dwarf_Debug /*dbg*/,
    Dwarf_Off          macro_offset,
    Dwarf_Unsigned      maximum_count,
    Dwarf_Signed        * entry_count,
    Dwarf_Macro_Details ** details,
    Dwarf_Error *       err);
```

dwarf\_get\_macro\_details() returns DW\_DLV\_OK and sets entry\_count to the number of details records returned through the details pointer. The data returned through details should be freed by a call to dwarf\_dealloc() with the allocation type DW\_DLA\_STRING. If DW\_DLV\_OK is returned, the entry\_count will be at least 1, since a compilation unit with macro information but no macros will have at least one macro data byte of 0.

dwarf\_get\_macro\_details() begins at the macro\_offset offset you supply and ends at the end of a compilation unit or at maximum\_count detail records (whichever comes first). If maximum\_count is 0, it is treated as if it were the maximum possible unsigned integer.

dwarf\_get\_macro\_details() attempts to set dmd\_fileindex to the correct file in every details record. If it is unable to do so (or whenever the current file index is unknown, it sets dmd\_fileindex to -1.

dwarf\_get\_macro\_details() returns DW\_DLV\_ERROR on error. It returns DW\_DLV\_NO\_ENTRY if there is no more macro information at that macro\_offset. If macro\_offset is passed in as 0, a DW\_DLV\_NO\_ENTRY return means there is no macro information.

```
Dwarf_Unsigned max = 0;
Dwarf_Off cur_off = 0;
Dwarf_Signed count = 0;
Dwarf_Macro_Details *maclist;
int errv;

/* Loop through all the compilation units macro info.
   This is not guaranteed to work because DWARF does not
   guarantee every byte in the section is meaningful:
   there can be garbage between the macro info
   for CUs. But this loop will usually work.
*/
while((errv = dwarf_get_macro_details(dbg, cur_off,max,
    &count,&maclist,&error))== DW_DLV_OK) {
    for (i = 0; i < count; ++i) {
        /* use maclist[i] */
    }
    cur_off = maclist[count-1].dmd_offset + 1;
    dwarf_dealloc(dbg, maclist, DW_DLA_STRING);
}
```

### 5.17 Low Level Frame Operations

These functions provide information about stack frames to be used to perform stack traces. The information is an abstraction of a table with a row per instruction and a column per register and a column

for the canonical frame address (CFA, which corresponds to the notion of a frame pointer), as well as a column for the return address.

From 1993-2006 the interface we'll here refer to as DWARF2 made the CFA be a column in the matrix, but left DW\_FRAME\_UNDEFINED\_VAL, and DW\_FRAME\_SAME\_VAL out of the matrix (giving them high numbers). As of the DWARF3 interfaces introduced in this document in April 2006, there are \*two\* interfaces (the original set and a new set). Several frame functions work transparently for either set, we will focus on the ones that are not equally suitable now.

The original DWARF2 interface set still exists (dwarf\_get\_fde\_info\_for\_reg(), dwarf\_get\_fde\_info\_for\_cfa\_reg(), and dwarf\_get\_fde\_info\_for\_all\_regs()) and works adequately for MIPS/IRIX DWARF2 and ABI/ISA sets that are sufficiently similar to MIPS. These functions not a good choice for non-MIPS architectures nor were they a good design for MIPS either. It's better to switch entirely to the new functions mentioned in the next paragraph. This DWARF2 interface set assumes and uses DW\_FRAME\_CFA\_COL and that is assumed when libdwarf is configured with --enable-oldframecol .

A new DWARF3 interface set of dwarf\_get\_fde\_info\_for\_reg3(), dwarf\_get\_fde\_info\_for\_cfa\_reg3(), dwarf\_get\_fde\_info\_for\_all\_regs3(), dwarf\_set\_frame\_rule\_table\_size() dwarf\_set\_frame\_cfa\_value(), dwarf\_set\_frame\_same\_value(), dwarf\_set\_frame\_undefined\_value(), and dwarf\_set\_frame\_rule\_initial\_value() is more flexible and will work for many more architectures. It is also entirely suitable for use with DWARF2 and DWARF4. The setting of the 'frame cfa column number' defaults to DW\_FRAME\_CFA\_COL3 and it can be set at runtime with dwarf\_set\_frame\_cfa\_value().

Mixing use of the DWARF2 interface set with use of the new DWARF3 interface set on a single open Dwarf\_Debug instance is a mistake. Do not do it.

We will pretend, from here on unless otherwise specified, that DW\_FRAME\_CFA\_COL3, DW\_FRAME\_UNDEFINED\_VAL, and DW\_FRAME\_SAME\_VAL are the synthetic column numbers. These columns may be user-chosen by calls of dwarf\_set\_frame\_cfa\_value() dwarf\_set\_frame\_undefined\_value(), and dwarf\_set\_frame\_same\_value() respectively.

Each cell in the table contains one of the following:

1. A register + offset(a)(b)
2. A register(c)(d)
3. A marker (DW\_FRAME\_UNDEFINED\_VAL) meaning *register value undefined*
4. A marker (DW\_FRAME\_SAME\_VAL) meaning *register value same as in caller*

(a old DWARF2 interface) When the column is DW\_FRAME\_CFA\_COL: the register number is a real hardware register, not a reference to DW\_FRAME\_CFA\_COL, not DW\_FRAME\_UNDEFINED\_VAL, and not DW\_FRAME\_SAME\_VAL. The CFA rule value should be the stack pointer plus offset 0 when no other value makes sense. A value of DW\_FRAME\_SAME\_VAL would be semi-logical, but since the CFA is not a real register, not really correct. A value of DW\_FRAME\_UNDEFINED\_VAL would imply the CFA is undefined -- this seems to be a useless notion, as the CFA is a means to finding real registers, so those real registers should be marked DW\_FRAME\_UNDEFINED\_VAL, and the CFA column content (whatever register it specifies) becomes unreferenced by anything.

(a new April 2006 DWARF2/3 interface): The CFA is separately accessible and not part of the table. The 'rule number' for the CFA is a number outside the table. So the CFA is a marker, not a register number. See DW\_FRAME\_CFA\_COL3 in libdwarf.h and dwarf\_get\_fde\_info\_for\_cfa\_reg3() and

dwarf\_set\_frame\_rule\_cfa\_value().

(b) When the column is not DW\_FRAME\_CFA\_COL3, the 'register' will and must be DW\_FRAME\_CFA\_COL3(COL), implying that to get the final location for the column one must add the offset here plus the DW\_FRAME\_CFA\_COL3 rule value.

(c) When the column is DW\_FRAME\_CFA\_COL3, then the 'register' number is (must be) a real hardware register . (This paragraph does not apply to the April 2006 new interface). If it were DW\_FRAME\_UNDEFINED\_VAL or DW\_FRAME\_SAME\_VAL it would be a marker, not a register number.

(d) When the column is not DW\_FRAME\_CFA\_COL3, the register may be a hardware register. It will not be DW\_FRAME\_CFA\_COL3.

There is no 'column' for DW\_FRAME\_UNDEFINED\_VAL or DW\_FRAME\_SAME\_VAL. Nor for DW\_FRAME\_CFA\_COL3.

Figure 3 is machine dependent and represents MIPS CPU register assignments. The DW\_FRAME\_CFA\_COL define in dwarf.h is historical and really belongs in libdwarf.h, not dwarf.h.

NAME	value	PURPOSE
DW_FRAME_CFA_COL	0	column used for CFA
DW_FRAME_REG1	1	integer register 1
DW_FRAME_REG2	2	integer register 2
---		obvious names and values here
DW_FRAME_REG30	30	integer register 30
DW_FRAME_REG31	31	integer register 31
DW_FRAME_FREG0	32	floating point register 0
DW_FRAME_FREG1	33	floating point register 1
---		obvious names and values here
DW_FRAME_FREG30	62	floating point register 30
DW_FRAME_FREG31	63	floating point register 31
DW_FRAME_RA_COL	64	column recording ra
DW_FRAME_UNDEFINED_VAL	1034	register val undefined
DW_FRAME_SAME_VAL	1035	register same as in caller

**Figure 4.** Frame Information Rule Assignments MIPS

The following table shows SGI/MIPS specific special cell values: these values mean that the cell has the value *undefined* or *same value* respectively, rather than containing a *register* or *register+offset*. It assumes DW\_FRAME\_CFA\_COL is a table rule, which is not readily accomplished or even sensible for some architectures.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value. Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as caller had. Not a column or register value
DW_FRAME_CFA_COL	0	means register zero is usurped by the CFA column.

**Figure 5.** Frame Information Special Values any architecture

The following table shows more general special cell values. These values mean that the cell register-



number refers to the *cfa-register* or *undefined-value* or *same-value* respectively, rather than referring to a *register in the table*. The generality arises from making DW\_FRAME\_CFA\_COL3 be outside the set of registers and making the cfa rule accessible from outside the rule-table.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value. Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as caller had. Not a column or register value
DW_FRAME_CFA_COL3	1436	means 'cfa register' is referred to, not a real register, not a column, but the cfa (the cfa does have a value, but in the DWARF3 libdwarf interface it does not have a 'real register number').

#### 5.17.0.1 dwarf\_get\_fde\_list()

```
int dwarf_get_fde_list(  
    Dwarf_Debug dbg,  
    Dwarf_Cie **cie_data,  
    Dwarf_Signed *cie_element_count,  
    Dwarf_Fde **fde_data,  
    Dwarf_Signed *fde_element_count,  
    Dwarf_Error *error);
```

dwarf\_get\_fde\_list() stores a pointer to a list of Dwarf\_Cie descriptors in \*cie\_data, and the count of the number of descriptors in \*cie\_element\_count. There is a descriptor for each CIE in the .debug\_frame section. Similarly, it stores a pointer to a list of Dwarf\_Fde descriptors in \*fde\_data, and the count of the number of descriptors in \*fde\_element\_count. There is one descriptor per FDE in the .debug\_frame section. dwarf\_get\_fde\_list() returns DW\_DLV\_ERROR on error. It returns DW\_DLV\_NO\_ENTRY if it cannot find frame entries. It returns DW\_DLV\_OK on a successful return.

On successful return, structures pointed to by a descriptor should be freed using dwarf\_fde\_cie\_list\_dealloc(). This dealloc approach is new as of July 15, 2005.

```
Dwarf_Signed cnt;  
Dwarf_Cie *cie_data;  
Dwarf_Signed cie_count;  
Dwarf_Fde *fde_data;  
Dwarf_Signed fde_count;  
int fres;  
  
fres = dwarf_get_fde_list(dbg,&cie_data,&cie_count,  
                          &fde_data,&fde_count,&error);  
if (fres == DW_DLV_OK) {  
    dwarf_fde_cie_list_dealloc(dbg, cie_data, cie_count,  
                              fde_data,fde_count);  
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did.

```
Dwarf_Signed cnt;
Dwarf_Cie *cie_data;
Dwarf_Signed cie_count;
Dwarf_Fde *fde_data;
Dwarf_Signed fde_count;
int fres;

fres = dwarf_get_fde_list(dbg,&cie_data,&cie_count,
                        &fde_data,&fde_count,&error);
if (fres == DW_DLV_OK) {

    for (i = 0; i < cie_count; ++i) {
        /* use cie[i] */
        dwarf_dealloc(dbg, cie_data[i], DW_DLA_CIE);
    }
    for (i = 0; i < fde_count; ++i) {
        /* use fde[i] */
        dwarf_dealloc(dbg, fde_data[i], DW_DLA_FDE);
    }
    dwarf_dealloc(dbg, cie_data, DW_DLA_LIST);
    dwarf_dealloc(dbg, fde_data, DW_DLA_LIST);
}
```

#### 5.17.0.2 dwarf\_get\_fde\_list\_eh()

```
int dwarf_get_fde_list_eh(
    Dwarf_Debug dbg,
    Dwarf_Cie **cie_data,
    Dwarf_Signed *cie_element_count,
    Dwarf_Fde **fde_data,
    Dwarf_Signed *fde_element_count,
    Dwarf_Error *error);
```

dwarf\_get\_fde\_list\_eh() is identical to dwarf\_get\_fde\_list() except that dwarf\_get\_fde\_list\_eh() reads the GNU gcc section named .eh\_frame (C++ exception handling information).

dwarf\_get\_fde\_list\_eh() stores a pointer to a list of Dwarf\_Cie descriptors in \*cie\_data, and the count of the number of descriptors in \*cie\_element\_count. There is a descriptor for each CIE in the .debug\_frame section. Similarly, it stores a pointer to a list of Dwarf\_Fde descriptors in \*fde\_data, and the count of the number of descriptors in \*fde\_element\_count. There is one descriptor per FDE in the .debug\_frame section. dwarf\_get\_fde\_list() returns DW\_DLV\_ERROR on error. It returns DW\_DLV\_NO\_ENTRY if it cannot find exception handling entries. It returns DW\_DLV\_OK on a successful return.

On successful return, structures pointed to by a descriptor should be freed using dwarf\_fde\_cie\_list\_dealloc(). This dealloc approach is new as of July 15, 2005.

```
Dwarf_Signed cnt;
Dwarf_Cie *cie_data;
Dwarf_Signed cie_count;
Dwarf_Fde *fde_data;
Dwarf_Signed fde_count;
int fres;

fres = dwarf_get_fde_list(dbg,&cie_data,&cie_count,
                        &fde_data,&fde_count,&error);
if (fres == DW_DLV_OK) {
    dwarf_fde_cie_list_dealloc(dbg, cie_data, cie_count,
                              fde_data,fde_count);
}
```

#### 5.17.0.3 dwarf\_get\_cie\_of\_fde()

```
int dwarf_get_cie_of_fde(Dwarf_Fde fde,
                        Dwarf_Cie *cie_returned,
                        Dwarf_Error *error);
```

`dwarf_get_cie_of_fde()` stores a `Dwarf_Cie` into the `Dwarf_Cie` that `cie_returned` points at.

If one has called `dwarf_get_fde_list` and does not wish to `dwarf_dealloc()` all the individual FDEs immediately, one must also avoid `dwarf_dealloc`-ing the CIEs for those FDEs not immediately `dealloc'd`. Failing to observe this restriction will cause the FDE(s) not `dealloc'd` to become invalid: an FDE contains (hidden in it) a CIE pointer which will be be invalid (stale, pointing to freed memory) if the CIE is `dealloc'd`. The invalid CIE pointer internal to the FDE cannot be detected as invalid by `libdwarf`. If one later passes an FDE with a stale internal CIE pointer to one of the routines taking an FDE as input the result will be failure of the call (returning `DW_DLV_ERROR`) at best and it is possible a coredump or worse will happen (eventually).

`dwarf_get_cie_of_fde()` returns `DW_DLV_OK` if it is successful (it will be unless `fde` is the `NULL` pointer). It returns `DW_DLV_ERROR` if the `fde` is invalid (`NULL`).

Each `Dwarf_Fde` descriptor describes information about the frame for a particular subroutine or function.

`int dwarf_get_fde_for_die` is SGI/MIPS specific.

#### 5.17.0.4 dwarf\_get\_fde\_for\_die()

```
int dwarf_get_fde_for_die(
    Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Fde * return_fde,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_get_fde_for_die()` returns `DW_DLV_OK` and sets `*return_fde` to a `Dwarf_Fde` descriptor representing frame information for the given `die`. It looks for the `DW_AT_MIPS_fde` attribute in the given `die`. If it finds it, it uses the value of the attribute as the offset in the `.debug_frame` section where the FDE begins. If there is no `DW_AT_MIPS_fde` it returns `DW_DLV_NO_ENTRY`. If there is an error it returns `DW_DLV_ERROR`.

#### 5.17.0.5 dwarf\_get\_fde\_range()

```
int dwarf_get_fde_range(  
    Dwarf_Fde fde,  
    Dwarf_Addr *low_pc,  
    Dwarf_Unsigned *func_length,  
    Dwarf_Ptr *fde_bytes,  
    Dwarf_Unsigned *fde_byte_length,  
    Dwarf_Off *cie_offset,  
    Dwarf_Signed *cie_index,  
    Dwarf_Off *fde_offset,  
    Dwarf_Error *error);
```

On success, dwarf\_get\_fde\_range( ) returns DW\_DLV\_OK.

The location pointed to by low\_pc is set to the low pc value for this function.

The location pointed to by func\_length is set to the length of the function in bytes. This is essentially the length of the text section for the function.

The location pointed to by fde\_bytes is set to the address where the FDE begins in the .debug\_frame section.

The location pointed to by fde\_byte\_length is set to the length in bytes of the portion of .debug\_frame for this FDE. This is the same as the value returned by dwarf\_get\_fde\_range.

The location pointed to by cie\_offset is set to the offset in the .debug\_frame section of the CIE used by this FDE.

The location pointed to by cie\_index is set to the index of the CIE used by this FDE. The index is the index of the CIE in the list pointed to by cie\_data as set by the function dwarf\_get\_fde\_list(). However, if the function dwarf\_get\_fde\_for\_die() was used to obtain the given fde, this index may not be correct.

The location pointed to by fde\_offset is set to the offset of the start of this FDE in the .debug\_frame section.

dwarf\_get\_fde\_range( ) returns DW\_DLV\_ERROR on error.

#### 5.17.0.6 dwarf\_get\_cie\_info()

```
int dwarf_get_cie_info(  
    Dwarf_Cie cie,  
    Dwarf_Unsigned *bytes_in_cie,  
    Dwarf_Small *version,  
    char **augmenter,  
    Dwarf_Unsigned *code_alignment_factor,  
    Dwarf_Signed *data_alignment_factor,  
    Dwarf_Half *return_address_register_rule,  
    Dwarf_Ptr *initial_instructions,  
    Dwarf_Unsigned *initial_instructions_length,  
    Dwarf_Error *error);
```

dwarf\_get\_cie\_info() is primarily for Internal-level Interface consumers. If successful, it returns DW\_DLV\_OK and sets \*bytes\_in\_cie to the number of bytes in the portion of the frames section for the CIE represented by the given Dwarf\_Cie descriptor, cie. The other fields are directly taken from the

cie and returned, via the pointers to the caller. It returns DW\_DLV\_ERROR on error.

#### 5.17.0.7 dwarf\_get\_cie\_index()

```
int dwarf_get_cie_index(  
    Dwarf_Cie cie,  
    Dwarf_Signed *cie_index,  
    Dwarf_Error *error);
```

On success, dwarf\_get\_cie\_index() returns DW\_DLV\_OK. On error this function returns DW\_DLV\_ERROR.

The location pointed to by cie\_index is set to the index of the CIE of this FDE. The index is the index of the CIE in the list pointed to by cie\_data as set by the function dwarf\_get\_fde\_list().

So one must have used dwarf\_get\_fde\_list() or dwarf\_get\_fde\_list\_eh() to get a cie list before this is meaningful.

This function is occasionally useful, but is little used.

#### 5.17.0.8 dwarf\_get\_fde\_instr\_bytes()

```
int dwarf_get_fde_instr_bytes(  
    Dwarf_Fde fde,  
    Dwarf_Ptr *outinstrs,  
    Dwarf_Unsigned *outlen,  
    Dwarf_Error *error);
```

dwarf\_get\_fde\_instr\_bytes() returns DW\_DLV\_OK and sets \*outinstrs to a pointer to a set of bytes which are the actual frame instructions for this fde. It also sets \*outlen to the length, in bytes, of the frame instructions. It returns DW\_DLV\_ERROR on error. It never returns DW\_DLV\_NO\_ENTRY. The intent is to allow low-level consumers like a dwarf-dumper to print the bytes in some fashion. The memory pointed to by outinstrs must not be changed and there is nothing to free.

#### 5.17.0.9 dwarf\_get\_fde\_info\_for\_reg()

This interface is suitable for DWARF2 but is not sufficient for DWARF3. See int dwarf\_get\_fde\_info\_for\_reg3.

```
int dwarf_get_fde_info_for_reg(  
    Dwarf_Fde fde,  
    Dwarf_Half table_column,  
    Dwarf_Addr pc_requested,  
    Dwarf_Signed *offset_relevant,  
    Dwarf_Signed *register_num,  
    Dwarf_Signed *offset,  
    Dwarf_Addr *row_pc,  
    Dwarf_Error *error);
```

dwarf\_get\_fde\_info\_for\_reg() returns DW\_DLV\_OK and sets \*offset\_relevant to non-zero if the offset is relevant for the row specified by pc\_requested and column specified by table\_column, for the FDE specified by fde. The intent is to return the rule for the given pc value and register. The location pointed to by register\_num is set to the register value for the rule. The location pointed to by offset is set to the offset value for the rule. If offset is not relevant for this rule, \*offset\_relevant is set to zero. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more

table rows with identical data (each such table row at a different pc value). Given a `pc_requested` which refers to a pc in such a group of identical rows, the location pointed to by `row_pc` is set to the lowest pc value within the group of identical rows. The value put in `*register_num` any of the `DW_FRAME_*` table columns values specified in `libdwarf.h` or `dwarf.h`.

`dwarf_get_fde_info_for_reg` returns `DW_DLV_ERROR` if there is an error.

It is usable with either `dwarf_get_fde_n()` or `dwarf_get_fde_at_pc()`.

`dwarf_get_fde_info_for_reg()` is tailored to MIPS, please use `dwarf_get_fde_info_for_reg3()` instead for all architectures.

#### 5.17.0.10 `dwarf_get_fde_info_for_all_regs()`

```
int dwarf_get_fde_info_for_all_regs(  
    Dwarf_Fde fde,  
    Dwarf_Addr pc_requested,  
    Dwarf_Regtable *reg_table,  
    Dwarf_Addr *row_pc,  
    Dwarf_Error *error);
```

`dwarf_get_fde_info_for_all_regs()` returns `DW_DLV_OK` and sets `*reg_table` for the row specified by `pc_requested` for the FDE specified by `fde`.

The intent is to return the rules for decoding all the registers, given a pc value. `reg_table` is an array of rules, one for each register specified in `dwarf.h`. The rule for each register contains three items - `dw_regnum` which denotes the register value for that rule, `dw_offset` which denotes the offset value for that rule and `dw_offset_relevant` which is set to zero if offset is not relevant for that rule. See `dwarf_get_fde_info_for_reg()` for a description of `row_pc`.

`dwarf_get_fde_info_for_all_regs` returns `DW_DLV_ERROR` if there is an error.

`int dwarf_get_fde_info_for_all_regs` is tailored to SGI/MIPS, please use `dwarf_get_fde_info_for_all_regs3()` instead for all architectures.

#### 5.17.0.11 `dwarf_set_frame_rule_table_size()`

This allows consumers to set the size of the (internal to libdwarf) rule table when using the 'reg3' interfaces (these interfaces are strongly preferred over the older 'reg' interfaces). It should be at least as large as the number of real registers in the ABI which is to be read in for the `dwarf_get_fde_info_for_reg3()` or `dwarf_get_fde_info_for_all_regs3()` functions to work properly.

The frame rule table size must be less than the marker values `DW_FRAME_UNDEFINED_VAL`, `DW_FRAME_SAME_VAL`, `DW_FRAME_CFA_COL3` (`dwarf_set_frame_rule_undefined_value()` `dwarf_set_frame_same_value()` `dwarf_set_frame_cfa_value()` effectively set these markers so the frame rule table size can actually be any value regardless of the macro values in `libdwarf.h` as long as the table size does not overlap these markers).

```
Dwarf_Half  
dwarf_set_frame_rule_table_size(Dwarf_Debug dbg,  
    Dwarf_Half value);
```

`dwarf_set_frame_rule_table_size()` sets the value `value` as the size of libdwarf-internal rules tables of `dbg`.

The function returns the previous value of the rules table size setting (taken from the dbg structure).

#### 5.17.0.12 dwarf\_set\_frame\_rule\_initial\_value()

This allows consumers to set the initial value for rows in the frame tables. By default it is taken from libdwarf.h and is DW\_FRAME\_REG\_INITIAL\_VALUE (which itself is either DW\_FRAME\_SAME\_VAL or DW\_FRAME\_UNDEFINED\_VAL). The MIPS/IRIX default is DW\_FRAME\_SAME\_VAL. Consumer code should set this appropriately and for many architectures (but probably not MIPS) DW\_FRAME\_UNDEFINED\_VAL is an appropriate setting. Note: an earlier spelling of dwarf\_set\_frame\_rule\_initial\_value() is still supported as an interface, but please change to use the new correctly spelled name.

```
Dwarf_Half
dwarf_set_frame_rule_initial_value(Dwarf_Debug dbg,
                                   Dwarf_Half value);
```

dwarf\_set\_frame\_rule\_initial\_value() sets the value value as the initial value for this dbg when initializing rules tables.

The function returns the previous value of initial value (taken from the dbg structure).

#### 5.17.0.13 dwarf\_set\_frame\_cfa\_value()

This allows consumers to set the number of the CFA register for rows in the frame tables. By default it is taken from libdwarf.h and is DW\_FRAME\_CFA\_COL. Consumer code should set this appropriately and for nearly all architectures DW\_FRAME\_CFA\_COL3 is an appropriate setting.

```
Dwarf_Half
dwarf_set_frame_rule_cfa_value(Dwarf_Debug dbg,
                               Dwarf_Half value);
```

dwarf\_set\_frame\_rule\_cfa\_value() sets the value value as the number of the cfa 'register rule' for this dbg when initializing rules tables.

The function returns the previous value of the pseudo-register (taken from the dbg structure).

#### 5.17.0.14 dwarf\_set\_frame\_same\_value()

This allows consumers to set the number of the pseudo-register when DW\_CFA\_same\_value is the operation. By default it is taken from libdwarf.h and is DW\_FRAME\_SAME\_VAL. Consumer code should set this appropriately, though for many architectures DW\_FRAME\_SAME\_VAL is an appropriate setting.

```
Dwarf_Half
dwarf_set_frame_rule_same_value(Dwarf_Debug dbg,
                                Dwarf_Half value);
```

dwarf\_set\_frame\_rule\_same\_value() sets the value value as the number of the register that is the pseudo-register set by the DW\_CFA\_same\_value frame operation.

The function returns the previous value of the pseudo-register (taken from the dbg structure).

#### 5.17.0.15 dwarf\_set\_frame\_undefined\_value()

This allows consumers to set the number of the pseudo-register when DW\_CFA\_undefined\_value is the operation. By default it is taken from libdwarf.h and is

DW\_FRAME\_UNDEFINED\_VAL. Consumer code should set this appropriately, though for many architectures DW\_FRAME\_UNDEFINED\_VAL is an appropriate setting.

```
Dwarf_Half
dwarf_set_frame_rule_undefined_value(Dwarf_Debug dbg,
    Dwarf_Half value);
```

dwarf\_set\_frame\_rule\_undefined\_value() sets the value value as the number of the register that is the pseudo-register set by the DW\_CFA\_undefined\_value frame operation.

The function returns the previous value of the pseudo-register (taken from the dbg structure).

#### 5.17.0.16 dwarf\_set\_default\_address\_size()

This allows consumers to set a default address size. When one has an object where the default address\_size does not match the frame address size where there is no debug\_info available to get a frame-specific address-size, this function is useful. For example, if an Elf64 object has a .debug\_frame whose real address\_size is 4 (32 bits). This a very rare situation.

```
Dwarf_Small
dwarf_set_default_address_size(Dwarf_Debug dbg,
    Dwarf_Small value);
```

dwarf\_set\_default\_address\_size() sets the value value as the default address size for this activation of the reader, but only if value is greater than zero (otherwise the default address size is not changed).

The function returns the previous value of the default address size (taken from the dbg structure).

#### 5.17.0.17 dwarf\_get\_fde\_info\_for\_reg3()

This interface is suitable for DWARF3 and DWARF2. It returns the values for a particular real register (Not for the CFA register, see dwarf\_get\_fde\_info\_for\_cfa\_reg3() below). If the application is going to retrieve the value for more than a few table\_column values at this pc\_requested (by calling this function multiple times) it is much more efficient to call dwarf\_get\_fde\_info\_for\_all\_regs3() (in spite of the additional setup that requires of the caller).

```
int dwarf_get_fde_info_for_reg3(
    Dwarf_Fde fde,
    Dwarf_Half table_column,
    Dwarf_Addr pc_requested,
    Dwarf_Small *value_type,
    Dwarf_Signed *offset_relevant,
    Dwarf_Signed *register_num,
    Dwarf_Signed *offset_or_block_len,
    Dwarf_Ptr *block_ptr,
    Dwarf_Addr *row_pc,
    Dwarf_Error *error);
```

dwarf\_get\_fde\_info\_for\_reg3() returns DW\_DLV\_OK on success. It sets \*value\_type to one of DW\_EXPR\_OFFSET (0), DW\_EXPR\_VAL\_OFFSET(1), DW\_EXPR\_EXPRESSION(2) or DW\_EXPR\_VAL\_EXPRESSION(3). On call, table\_column must be set to the register number of a real register. Not the cfa 'register' or DW\_FRAME\_SAME\_VALUE or DW\_FRAME\_UNDEFINED\_VALUE.



if `*value_type` has the value `DW_EXPR_OFFSET` (0) then:

It sets `*offset_relevant` to non-zero if the offset is relevant for the row specified by `pc_requested` and column specified by `table_column` or, for the FDE specified by `fde`. In this case the `*register_num` will be set to `DW_FRAME_CFA_COL3` (. This is an offset(N) rule as specified in the DWARF3/2 documents. Adding the value of `*offset_or_block_len` to the value of the CFA register gives the address of a location holding the previous value of register `table_column`.

If offset is not relevant for this rule, `*offset_relevant` is set to zero. `*register_num` will be set to the number of the real register holding the value of the `table_column` register. This is the register(R) rule as specified in DWARF3/2 documents.

The intent is to return the rule for the given pc value and register. The location pointed to by `register_num` is set to the register value for the rule. The location pointed to by `offset` is set to the offset value for the rule. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more table rows with identical data (each such table row at a different pc value). Given a `pc_requested` which refers to a pc in such a group of identical rows, the location pointed to by `row_pc` is set to the lowest pc value within the group of identical rows.

If `*value_type` has the value `DW_EXPR_VAL_OFFSET` (1) then:

This will be a `val_offset(N)` rule as specified in the DWARF3/2 documents so `*offset_relevant` will be non zero. The calculation is identical to the `DW_EXPR_OFFSET` (0) calculation with `*offset_relevant` non-zero, but the value resulting is the actual `table_column` value (rather than the address where the value may be found).

If `*value_type` has the value `DW_EXPR_EXPRESSION` (1) then:

`*offset_or_block_len` is set to the length in bytes of a block of memory with a DWARF expression in the block. `*block_ptr` is set to point at the block of memory. The consumer code should evaluate the block as a DWARF-expression. The result is the address where the previous value of the register may be found. This is a DWARF3/2 `expression(E)` rule.

If `*value_type` has the value `DW_EXPR_VAL_EXPRESSION` (1) then:

The calculation is exactly as for `DW_EXPR_EXPRESSION` (1) but the result of the DWARF-expression evaluation is the value of the `table_column` (not the address of the value). This is a DWARF3/2 `val_expression(E)` rule.

`dwarf_get_fde_info_for_reg` returns `DW_DLV_ERROR` if there is an error and if there is an error only the error pointer is set, none of the other output arguments are touched.

It is usable with either `dwarf_get_fde_n( )` or `dwarf_get_fde_at_pc( )`.

#### 5.17.0.18 `dwarf_get_fde_info_for_cfa_reg3()`

```
int dwarf_get_fde_info_for_cfa_reg3(Dwarf_Fde fde,
    Dwarf_Addr      pc_requested,
    Dwarf_Small *    value_type,
    Dwarf_Signed*    offset_relevant,
    Dwarf_Signed*    register_num,
    Dwarf_Signed*    offset_or_block_len,
    Dwarf_Ptr *      block_ptr ,
    Dwarf_Addr *      row_pc_out,
    Dwarf_Error *     error)
```

This is identical to `dwarf_get_fde_info_for_reg3()` except the returned values are for the CFA rule. So register number `*register_num` will be set to a real register, not one of the pseudo registers (which are usually `DW_FRAME_CFA_COL3`, `DW_FRAME_SAME_VALUE`, or `DW_FRAME_UNDEFINED_VALUE`).

#### 5.17.0.19 dwarf\_get\_fde\_info\_for\_all\_regs3()

```
int dwarf_get_fde_info_for_all_regs3(
    Dwarf_Fde fde,
    Dwarf_Addr pc_requested,
    Dwarf_Regtable3 *reg_table,
    Dwarf_Addr *row_pc,
    Dwarf_Error *error)
```

`dwarf_get_fde_info_for_all_regs3()` returns `DW_DLV_OK` and sets `*reg_table` for the row specified by `pc_requested` for the FDE specified by `fde`. The intent is to return the rules for decoding all the registers, given a pc value. `reg_table` is an array of rules, the array size specified by the caller. plus a rule for the CFA. The rule for the cfa returned in `*reg_table` defines the CFA value at `pc_requested`. The rule for each register contains several values that enable the consumer to determine the previous value of the register (see the earlier documentation of `Dwarf_Regtable3`). `dwarf_get_fde_info_for_reg3()` and the `Dwarf_Regtable3` documentation above for a description of the values for each row.

`dwarf_get_fde_info_for_all_regs3` returns `DW_DLV_ERROR` if there is an error.

It is up to the caller to allocate space for `*reg_table` and initialize it properly.

#### 5.17.0.20 dwarf\_get\_fde\_n()

```
int dwarf_get_fde_n(
    Dwarf_Fde *fde_data,
    Dwarf_Unsigned fde_index,
    Dwarf_Fde *returned_fde,
    Dwarf_Error *error)
```

`dwarf_get_fde_n()` returns `DW_DLV_OK` and sets `returned_fde` to the `Dwarf_Fde` descriptor whose index is `fde_index` in the table of `Dwarf_Fde` descriptors pointed to by `fde_data`. The index starts with 0. The table pointed to by `fde_data` is required to contain at least one entry. If the table has no entries at all the error checks may refer to uninitialized memory. Returns `DW_DLV_NO_ENTRY` if the index does not exist in the table of `Dwarf_Fde` descriptors. Returns `DW_DLV_ERROR` if there is an error. This function cannot be used unless the block of `Dwarf_Fde` descriptors has been created by a call to `dwarf_get_fde_list()`.

#### 5.17.0.21 dwarf\_get\_fde\_at\_pc()

```
int dwarf_get_fde_at_pc(
    Dwarf_Fde *fde_data,
    Dwarf_Addr pc_of_interest,
    Dwarf_Fde *returned_fde,
    Dwarf_Addr *lopc,
    Dwarf_Addr *hipc,
    Dwarf_Error *error)
```

`dwarf_get_fde_at_pc()` returns `DW_DLV_OK` and sets `returned_fde` to a `Dwarf_Fde` descriptor for a function which contains the `pc` value specified by `pc_of_interest`. In addition, it sets the locations pointed to by `lopc` and `hipc` to the low address and the high address covered by this FDE, respectively. The table pointed to by `fde_data` is required to contain at least one entry. If the table has no entries at all the error checks may refer to uninitialized memory. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if `pc_of_interest` is not in any of the FDEs represented by the block of `Dwarf_Fde` descriptors pointed to by `fde_data`. This function cannot be used unless the block of `Dwarf_Fde` descriptors has been created by a call to `dwarf_get_fde_list()`.

#### 5.17.0.22 dwarf\_expand\_frame\_instructions()

```
int dwarf_expand_frame_instructions(
    Dwarf_Cie cie,
    Dwarf_Ptr instruction,
    Dwarf_Unsigned i_length,
    Dwarf_Frame_Op **returned_op_list,
    Dwarf_Signed * returned_op_count,
    Dwarf_Error *error);
```

`dwarf_expand_frame_instructions()` is a High-level interface function which expands a frame instruction byte stream into an array of `Dwarf_Frame_Op` structures. To indicate success, it returns `DW_DLV_OK`. The address where the byte stream begins is specified by `instruction`, and the length of the byte stream is specified by `i_length`. The location pointed to by `returned_op_list` is set to point to a table of `returned_op_count` pointers to `Dwarf_Frame_Op` which contain the frame instructions in the byte stream. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. After a successful return, the array of structures should be freed using `dwarf_dealloc()` with the allocation type `DW_DLA_FRAME_BLOCK` (when they are no longer of interest).

Not all CIEs have the same address-size, so it is crucial that a CIE pointer to the frame's CIE be passed in.

```
Dwarf_Signed cnt;
Dwarf_Frame_Op *frameops;
Dwarf_Ptr instruction;
Dwarf_Unsigned len;
int res;

res = expand_frame_instructions(dbg,instruction,len, &frameops,&cnt, &error);
if (res == DW_DLV_OK) {
    for (i = 0; i < cnt; ++i) {
        /* use frameops[i] */
    }
    dwarf_dealloc(dbg, frameops, DW_DLA_FRAME_BLOCK);
}
```

#### 5.17.0.23 dwarf\_get\_fde\_exception\_info()

```
int dwarf_get_fde_exception_info(  
    Dwarf_Fde fde,  
    Dwarf_Signed * offset_into_exception_tables,  
    Dwarf_Error * error);
```

dwarf\_get\_fde\_exception\_info() is an IRIX specific function which returns an exception table signed offset through offset\_into\_exception\_tables. The function never returns DW\_DLV\_NO\_ENTRY. If DW\_DLV\_NO\_ENTRY is NULL the function returns DW\_DLV\_ERROR. For non-IRIX objects the offset returned will always be zero. For non-C++ objects the offset returned will always be zero. The meaning of the offset and the content of the tables is not defined in this document. The applicable CIE augmentation string (see above) determines whether the value returned has meaning.

### 5.18 Location Expression Evaluation

An "interpreter" which evaluates a location expression is required in any debugger. There is no interface defined here at this time.

One problem with defining an interface is that operations are machine dependent: they depend on the interpretation of register numbers and the methods of getting values from the environment the expression is applied to.

It would be desirable to specify an interface.

#### 5.18.1 Location List Internal-level Interface

##### 5.18.1.1 dwarf\_get\_loclist\_entry()

```
int dwarf_get_loclist_entry(  
    Dwarf_Debug dbg,  
    Dwarf_Unsigned offset,  
    Dwarf_Addr *hpc_offset,  
    Dwarf_Addr *lopc_offset,  
    Dwarf_Ptr *data,  
    Dwarf_Unsigned *entry_len,  
    Dwarf_Unsigned *next_entry,  
    Dwarf_Error *error)
```

The function reads a location list entry starting at offset and returns through pointers (when successful) the high pc hpc\_offset, low pc lopc\_offset, a pointer to the location description data data, the length of the location description data entry\_len, and the offset of the next location description entry next\_entry.

This function will usually work correctly (meaning with most objects) but will not work correctly (and can crash an application calling it) if either some location list applies to a compilation unit with an address\_size different from the overall address\_size of the object file being read or if the .debug\_loc section being read has random padding bytes between loclists. Neither of these characteristics necessarily represents a bug in the compiler/linker toolset that produced the object file being read. The DWARF standard allows both characteristics.

dwarf\_dwarf\_get\_loclist\_entry() returns DW\_DLV\_OK if successful. DW\_DLV\_NO\_ENTRY is returned when the offset passed in is beyond the end of the .debug\_loc section (expected if you start at offset zero and proceed through all the entries). DW\_DLV\_ERROR is returned on error.

The `hipc_offset`, low pc `lopc_offset` are offsets from the beginning of the current procedure, not genuine pc values.

```
/* Looping through the dwarf_loc section finding loclists:
   an example. */
int res;
Dwarf_Unsigned next_entry;
Dwarf_Unsigned offset=0;
Dwarf_Addr hipc_off;
Dwarf_Addr lopc_off;
Dwarf_Ptr data;
Dwarf_Unsigned entry_len;
Dwarf_Unsigned next_entry;
Dwarf_Error err;

for(;;) {
    res = dwarf_get_loclist_entry(dbg,newoffset,&hipc_off,
                                &lopc_off, &data, &entry_len,&next_entry,&err);
    if (res == DW_DLV_OK) {
        /* A valid entry. */
        newoffset = next_entry;
        continue;
    } else if (res ==DW_DLV_NO_ENTRY) {
        /* Done! */
        break;
    } else {
        /* Error! */
        break;
    }
}
}
```

## 5.19 Abbreviations access

These are Internal-level Interface functions. Debuggers can ignore this.

### 5.19.1 dwarf\_get\_abbrev()

```
int dwarf_get_abbrev(
    Dwarf_Debug dbg,
    Dwarf_Unsigned offset,
    Dwarf_Abbrev *returned_abbrev,
    Dwarf_Unsigned *length,
    Dwarf_Unsigned *attr_count,
    Dwarf_Error *error)
```

The function `dwarf_get_abbrev()` returns `DW_DLV_OK` and sets `*returned_abbrev` to `Dwarf_Abbrev` descriptor for an abbreviation at offset `*offset` in the abbreviations section (i.e `.debug_abbrev`) on success. The user is responsible for making sure that a valid abbreviation begins at `offset` in the abbreviations section. The location pointed to by `length` is set to the length in bytes of the abbreviation in the abbreviations section. The location pointed to by `attr_count` is set to the

number of attributes in the abbreviation. An abbreviation entry with a length of 1 is the 0 byte of the last abbreviation entry of a compilation unit. `dwarf_get_abbrev()` returns `DW_DLV_ERROR` on error. If the call succeeds, the storage pointed to by `*returned_abbrev` should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ABBREV` when no longer needed.

### 5.19.2 dwarf\_get\_abbrev\_tag()

```
int dwarf_get_abbrev_tag(  
    Dwarf_abbrev abbrev,  
    Dwarf_Half *return_tag,  
    Dwarf_Error *error);
```

If successful, `dwarf_get_abbrev_tag()` returns `DW_DLV_OK` and sets `*return_tag` to the *tag* of the given abbreviation. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

### 5.19.3 dwarf\_get\_abbrev\_code()

```
int dwarf_get_abbrev_code(  
    Dwarf_abbrev abbrev,  
    Dwarf_Unsigned *return_code,  
    Dwarf_Error *error);
```

If successful, `dwarf_get_abbrev_code()` returns `DW_DLV_OK` and sets `*return_code` to the abbreviation code of the given abbreviation. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

### 5.19.4 dwarf\_get\_abbrev\_children\_flag()

```
int dwarf_get_abbrev_children_flag(  
    Dwarf_Abbrev abbrev,  
    Dwarf_Signed *returned_flag,  
    Dwarf_Error *error)
```

The function `dwarf_get_abbrev_children_flag()` returns `DW_DLV_OK` and sets `returned_flag` to `DW_children_no` (if the given abbreviation indicates that a die with that abbreviation has no children) or `DW_children_yes` (if the given abbreviation indicates that a die with that abbreviation has a child). It returns `DW_DLV_ERROR` on error.

### 5.19.5 dwarf\_get\_abbrev\_entry()

```
int dwarf_get_abbrev_entry(  
    Dwarf_Abbrev abbrev,  
    Dwarf_Signed index,  
    Dwarf_Half *attr_num,  
    Dwarf_Signed *form,  
    Dwarf_Off *offset,  
    Dwarf_Error *error)
```

If successful, `dwarf_get_abbrev_entry()` returns `DW_DLV_OK` and sets `*attr_num` to the attribute code of the attribute whose index is specified by `index` in the given abbreviation. The index starts at 0. The location pointed to by `form` is set to the form of the attribute. The location pointed to by `offset` is set to the byte offset of the attribute in the abbreviations section. It returns `DW_DLV_NO_ENTRY` if the index specified is outside the range of attributes in this abbreviation. It returns

DW\_DLV\_ERROR on error.

## 5.20 String Section Operations

The `.debug_str` section contains only strings. Debuggers need never use this interface: it is only for debugging problems with the string section itself.

### 5.20.1 dwarf\_get\_str()

```
int dwarf_get_str(  
    Dwarf_Debug dbg,  
    Dwarf_Off offset,  
    char **string,  
    Dwarf_Signed *returned_str_len,  
    Dwarf_Error *error)
```

The function `dwarf_get_str()` returns `DW_DLV_OK` and sets `*returned_str_len` to the length of the string, not counting the null terminator, that begins at the offset specified by `offset` in the `.debug_str` section. The location pointed to by `string` is set to a pointer to this string. The next string in the `.debug_str` section begins at the previous `offset + 1 + *returned_str_len`. A zero-length string is NOT the end of the section. If there is no `.debug_str` section, `DW_DLV_NO_ENTRY` is returned. If there is an error, `DW_DLV_ERROR` is returned. If we are at the end of the section (that is, `offset` is one past the end of the section) `DW_DLV_NO_ENTRY` is returned. If the `offset` is some other too-large value then `DW_DLV_ERROR` is returned.

## 5.21 Address Range Operations

These functions provide information about address ranges. Address ranges map ranges of pc values to the corresponding compilation-unit die that covers the address range.

### 5.21.1 dwarf\_get\_aranges()

```
int dwarf_get_aranges(  
    Dwarf_Debug dbg,  
    Dwarf_Arange **aranges,  
    Dwarf_Signed * returned_arange_count,  
    Dwarf_Error *error)
```

The function `dwarf_get_aranges()` returns `DW_DLV_OK` and sets `*returned_arange_count` to the count of the number of address ranges in the `.debug_aranges` section (for all compilation units). It sets `*aranges` to point to a block of `Dwarf_Arange` descriptors, one for each address range. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if there is no `.debug_aranges` section.

```
Dwarf_Signed cnt;
Dwarf_Arange *arang;
int res;

res = dwarf_get_aranges(dbg, &arang,&cnt, &error);
if (res == DW_DLV_OK) {

    for (i = 0; i < cnt; ++i) {
        /* use arang[i] */
        dwarf_dealloc(dbg, arang[i], DW_DLA_ARANGE);
    }
    dwarf_dealloc(dbg, arang, DW_DLA_LIST);
}
```

### 5.21.2 dwarf\_get\_arange()

```
int dwarf_get_arange(
    Dwarf_Arange *aranges,
    Dwarf_Unsigned arange_count,
    Dwarf_Addr address,
    Dwarf_Arange *returned_arange,
    Dwarf_Error *error);
```

The function `dwarf_get_arange()` takes as input a pointer to a block of `Dwarf_Arange` pointers, and a count of the number of descriptors in the block. It then searches for the descriptor that covers the given address. If it finds one, it returns `DW_DLV_OK` and sets `*returned_arange` to the descriptor. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if there is no `.debug_aranges` entry covering that address.

### 5.21.3 dwarf\_get\_cu\_die\_offset()

```
int dwarf_get_cu_die_offset(
    Dwarf_Arange arange,
    Dwarf_Off *returned_cu_die_offset,
    Dwarf_Error *error);
```

The function `dwarf_get_cu_die_offset()` takes a `Dwarf_Arange` descriptor as input, and if successful returns `DW_DLV_OK` and sets `*returned_cu_die_offset` to the offset in the `.debug_info` section of the compilation-unit DIE for the compilation-unit represented by the given address range. It returns `DW_DLV_ERROR` on error.

### 5.21.4 dwarf\_get\_arange\_cu\_header\_offset()

```
int dwarf_get_arange_cu_header_offset(
    Dwarf_Arange arange,
    Dwarf_Off *returned_cu_header_offset,
    Dwarf_Error *error)
```

The function `dwarf_get_arange_cu_header_offset()` takes a `Dwarf_Arange` descriptor as input, and if successful returns `DW_DLV_OK` and sets `*returned_cu_header_offset` to the offset in the `.debug_info` section of the compilation-unit header for the compilation-unit represented by the given



address range. It returns DW\_DLV\_ERROR on error.

This function added Rev 1.45, June, 2001.

This function is declared as 'optional' in libdwarf.h on IRIX systems so the \_MIPS\_SYMBOL\_PRESENT predicate may be used at run time to determine if the version of libdwarf linked into an application has this function.

### 5.21.5 dwarf\_get\_arange\_info()

```
int dwarf_get_arange_info(  
    Dwarf_Arange arange,  
    Dwarf_Addr *start,  
    Dwarf_Unsigned *length,  
    Dwarf_Off *cu_die_offset,  
    Dwarf_Error *error)
```

The function dwarf\_get\_arange\_info() returns DW\_DLV\_OK and stores the starting value of the address range in the location pointed to by start, the length of the address range in the location pointed to by length, and the offset in the .debug\_info section of the compilation-unit DIE for the compilation-unit represented by the address range. It returns DW\_DLV\_ERROR on error.

## 5.22 General Low Level Operations

This function is low-level and intended for use only by programs such as dwarf-dumpers.

### 5.22.1 dwarf\_get\_address\_size()

```
int dwarf_get_address_size(Dwarf_Debug dbg,  
    Dwarf_Half *addr_size,  
    Dwarf_Error *error)
```

The function dwarf\_get\_address\_size() returns DW\_DLV\_OK on success and sets the \*addr\_size to the size in bytes of an address. In case of error, it returns DW\_DLV\_ERROR and does not set \*addr\_size.

The address size returned is the overall address size, which can be misleading if different compilation units have different address sizes. Many ABIs have only a single address size per executable, but differing address sizes are becoming more common.

Use dwarf\_get\_die\_address\_size() instead whenever possible.

### 5.22.2 dwarf\_get\_die\_address\_size()

```
int dwarf_get_die_address_size(Dwarf_Die die,  
    Dwarf_Half *addr_size,  
    Dwarf_Error *error)
```

The function dwarf\_get\_die\_address\_size() returns DW\_DLV\_OK on success and sets the \*addr\_size to the size in bytes of an address. In case of error, it returns DW\_DLV\_ERROR and does not set \*addr\_size.

The address size returned is the address size of the compilation unit owning the die

This is the preferred way to get address size when the Dwarf\_Die is known.

## 5.23 Ranges Operations (.debug\_ranges)

### 5.24 Ranges Operations (.debug\_ranges)

These functions provide information about the address ranges indicated by a DW\_AT\_ranges attribute (the ranges are recorded in the .debug\_ranges section) of a DIE. Each call of dwarf\_get\_ranges\_a() or dwarf\_get\_ranges() returns an array of Dwarf\_Ranges structs, each of which represents a single ranges entry. The struct is defined in libdwarf.h.

#### 5.24.1 dwarf\_get\_ranges()

This is the original call and it will work fine when all compilation units have the same address\_size. There is no die argument to this original version of the function. Other arguments (and deallocation) match the use of dwarf\_get\_ranges\_a() (described next).

#### 5.24.2 dwarf\_get\_ranges\_a()

```
int dwarf_get_ranges_a(
    Dwarf_Debug dbg,
    Dwarf_Off offset,
    Dwarf_Die die,
    Dwarf_Ranges **ranges,
    Dwarf_Signed * returned_ranges_count,
    Dwarf_Unsigned * returned_byte_count,
    Dwarf_Error *error)
```

The function dwarf\_get\_ranges\_a() returns DW\_DLV\_OK and sets \*returned\_ranges\_count to the count of the number of address ranges in the group of ranges in the .debug\_ranges section at offset (which ends with a pair of zeros of pointer-size). This function is new as of 27 April 2009.

The offset argument should be the value of a DW\_AT\_ranges attribute of a Debugging Information Entry.

The die argument should be the value of a Dwarf\_Die pointer of a Dwarf\_Die with the attribute containing this range set offset. Because each compilation unit has its own address\_size field this argument is necessary to correctly read ranges. (Most executables have the same address\_size in every compilation unit, but some ABIs allow multiple address sized in an executable). If a NULL pointer is passed in libdwarf assumes a single address\_size is appropriate for all ranges records.

The call sets \*ranges to point to a block of Dwarf\_Ranges structs, one for each address range. It returns DW\_DLV\_ERROR on error. It returns DW\_DLV\_NO\_ENTRY if there is no .debug\_ranges section or if offset is past the end of the .debug\_ranges section.

If the \*returned\_byte\_count pointer is passed as non-NULL the number of bytes that the returned ranges were taken from is returned through the pointer (for example if the returned\_ranges\_count is 2 and the pointer-size is 4, then returned\_byte\_count will be 8). If the \*returned\_byte\_count pointer is passed as NULL the parameter is ignored. The \*returned\_byte\_count is only of use to certain dumper applications, most applications will not use it.

```
Dwarf_Signed cnt;
Dwarf_Ranges *ranges;
Dwarf_Unsigned bytes;
int res;
res = dwarf_get_ranges_a(dbg, off, dieptr, &ranges, &cnt, &bytes, &error);
if (res == DW_DLV_OK) {
    Dwarf_Signed i;
    for( i = 0; i < cnt; ++i ) {
        Dwarf_Ranges *cur = ranges+i;
        /* Use cur. */
    }
    dwarf_ranges_dealloc(dbg, ranges, cnt);
}
```

### 5.24.3 dwarf\_ranges\_dealloc()

```
int dwarf_ranges_dealloc(
    Dwarf_Debug dbg,
    Dwarf_Ranges *ranges,
    Dwarf_Signed range_count,
);
```

The function `dwarf_ranges_dealloc()` takes as input a pointer to a block of `Dwarf_Ranges` array and the number of structures in the block. It frees all the data in the array of structures.

## 5.25 TAG ATTR etc names as strings

These functions turn a value into a string. So applications wanting the string "DW\_TAG\_compile\_unit" given the value 0x11 (the value defined for this TAG) can do so easily.

The general form is

```
int dwarf_get_<something>_name(
    unsigned value,
    char **s_out,
);
```

If the value passed in is known, the function returns `DW_DLV_OK` and places a pointer to the appropriate string into `*s_out`. The string is in static storage and applications must never free the string. If the value is not known, `DW_DLV_NO_ENTRY` is returned and `*s_out` is not set. `DW_DLV_ERROR` is never returned.

Libdwarf generates these functions at libdwarf build time by reading dwarf.h.

All these follow this pattern rigidly, so the details of each are not repeated for each function.

The choice of 'unsigned' for the value type argument (the code value) argument is somewhat arbitrary, 'int' could have been used.

The library simply assumes the value passed in is applicable. So, for example, passing a TAG value code to `dwarf_get_ACCESS_name()` is a coding error which libdwarf will process as if it was an accessibility code value. Examples of bad and good usage are:

```
const char * out;
int res;
/* The following is wrong, do not do it! */
res = dwarf_get_ACCESS_name(DW_TAG_entry_point,&out);
/* Nothing one does here with 'res' or 'out'
   is meaningful. */

/* The following is meaningful.*/
res = dwarf_get_TAG_name(DW_TAG_entry_point,&out);
if( res == DW_DLV_OK) {
    /* Here 'out' is a pointer one can use which
       points to the string "DW_TAG_entry_point". */
} else {
    /* Here 'out' has not been touched, it is
       uninitialized. Do not use it. */
}
```

### 5.26 dwarf\_get\_ACCESS\_name()

Returns an accessibility code name through the `s_out` pointer.

### 5.27 dwarf\_get\_AT\_name()

Returns an attribute code name through the `s_out` pointer.

### 5.28 dwarf\_get\_ATE\_name()

Returns a base type encoding name through the `s_out` pointer.

### 5.29 dwarf\_get\_ADDR\_name()

Returns an address type encoding name through the `s_out` pointer. As of this writing only `DW_ADDR_none` is defined in `dwarf.h`.

### 5.30 dwarf\_get\_ATCF\_name()

Returns a SUN code flag encoding name through the `s_out` pointer. This code flag is entirely a DWARF extension.

### 5.31 dwarf\_get\_CHILDREN\_name()

Returns a child determination name (which is seen in the abbreviations section data) through the `s_out` pointer. The only value this recognizes for a 'yes' value is 1. As a flag value this is not quite correct (any non-zero value means yes) but dealing with this is left up to client code (normally compilers really do emit a value of 1 for a flag).

### 5.32 dwarf\_get\_children\_name()

Returns a child determination name through the `s_out` pointer, though this version is really a libdwarf artifact. The standard function is `dwarf_get_CHILDREN_name()` which appears just above. As a flag value this is not quite correct (any non-zero value means yes) but dealing with this is left up to client code (normally compilers really do emit a value of 1 for a flag).

### **5.33 dwarf\_get\_CC\_name()**

Returns a calling convention case code name through the `s_out` pointer.

### **5.34 dwarf\_get\_CFA\_name()**

Returns a call frame information instruction name through the `s_out` pointer.

### **5.35 dwarf\_get\_DS\_name()**

Returns a decimal sign code name through the `s_out` pointer.

### **5.36 dwarf\_get\_DSC\_name()**

Returns a discriminant descriptor code name through the `s_out` pointer.

### **5.37 dwarf\_get\_EH\_name()**

Returns a GNU exception header code name through the `s_out` pointer.

### **5.38 dwarf\_get\_END\_name()**

Returns an endian code name through the `s_out` pointer.

### **5.39 dwarf\_get\_FORM\_name()**

Returns an form code name through the `s_out` pointer.

### **5.40 dwarf\_get\_FRAME\_name()**

Returns a frame code name through the `s_out` pointer. These are dependent on the particular ABI, so unless the `dwarf.h` used to generate `libdwarf` matches your ABI these names are unlikely to be very useful and certainly won't be entirely appropriate.

### **5.41 dwarf\_get\_ID\_name()**

Returns an identifier case code name through the `s_out` pointer.

### **5.42 dwarf\_get\_INL\_name()**

Returns an inline code name through the `s_out` pointer.

### **5.43 dwarf\_get\_LANG\_name()**

Returns a language code name through the `s_out` pointer.

### **5.44 dwarf\_get\_LNE\_name()**

Returns a line table extended opcode code name through the `s_out` pointer.

### **5.45 dwarf\_get\_LNS\_name()**

Returns a line table standard opcode code name through the `s_out` pointer.

### **5.46 dwarf\_get\_MACINFO\_name()**

Returns a macro information `macinfo` code name through the `s_out` pointer.

### **5.47 dwarf\_get\_OP\_name()**

Returns a DWARF expression operation code name through the `s_out` pointer.

### 5.48 dwarf\_get\_ORD\_name()

Returns an array ordering code name through the `s_out` pointer.

### 5.49 dwarf\_get\_TAG\_name()

Returns a TAG name through the `s_out` pointer.

### 5.50 dwarf\_get\_VIRTUALITY\_name()

Returns a virtuality code name through the `s_out` pointer.

### 5.51 dwarf\_get\_VIS\_name()

Returns a visibility code name through the `s_out` pointer.

## 5.52 Section Operations

In checking DWARF in linkonce sections for correctness it has been found useful to have certain section-oriented operations when processing object files. Normally these operations are not needed or useful in a fully-linked executable or shared library.

While the code is written with Elf sections in mind, it is quite possible to process non-Elf objects with code that implements certain function pointers (see `struct Dwarf_Obj_Access_interface_s`).

So far no one with such non-elf code has come forward to open-source it.

### 5.52.1 dwarf\_get\_section\_count()

```
int dwarf_get_section_count(  
    Dwarf_Debug dbg)
```

Returns a count of the number of object sections found.

### 5.52.2 dwarf\_get\_section\_info\_by\_name()

```
int dwarf_get_section_info_by_name(  
    const char *section_name,  
    Dwarf_Addr *section_addr,  
    Dwarf_Unsigned *section_size,  
    Dwarf_Error *error)
```

The function `dwarf_get_section_info_by_name()` returns `DW_DLX_OK` if the section given by `section_name` was seen by `libdwarf`. On success it sets `*section_addr` to the virtual address assigned to the section by the linker or compiler and `*section_size` to the size of the object section.

It returns `DW_DLX_ERROR` on error.

### 5.52.3 dwarf\_get\_section\_info\_by\_index()

```
int dwarf_get_section_info_by_index(  
    int section_index,  
    const char **section_name,  
    Dwarf_Addr *section_addr,  
    Dwarf_Unsigned *section_size,  
    Dwarf_Error *error)
```

The function `dwarf_get_section_info_by_index()` returns `DW_DLV_OK` if the section given by `section_index` was seen by `libdwarf`. `*section_addr` to the virtual address assigned to the section by the linker or compiler and `*section_size` to the size of the object section.

No free or deallocate of information returned should be done by callers.

## 5.53 Utility Operations

These functions aid in the management of errors encountered when using functions in the *libdwarf* library and releasing memory allocated as a result of a *libdwarf* operation.

For clients that wish to encode LEB numbers two interfaces are provided to the producer code's internal LEB function.

### 5.53.1 dwarf\_errno()

```
Dwarf_Unsigned dwarf_errno(  
    Dwarf_Error error)
```

The function `dwarf_errno()` returns the error number corresponding to the error specified by `error`.

### 5.53.2 dwarf\_errmsg()

```
const char* dwarf_errmsg(  
    Dwarf_Error error)
```

The function `dwarf_errmsg()` returns a pointer to a null-terminated error message string corresponding to the error specified by `error`. The string returned by `dwarf_errmsg()` should not be deallocated using `dwarf_dealloc()`.

### 5.53.3 dwarf\_get\_harmless\_error\_list()

```
int dwarf_get_harmless_error_list(Dwarf_Debug dbg,  
    unsigned count,  
    const char **errmsg_ptrs_array,  
    unsigned *newerr_count);
```

The harmless errors are not denoted by error returns from the other `libdwarf` functions. Instead, this function returns strings of any harmless errors that have been seen in the current object. Clients never need call this, but if a client wishes to report any such errors it may call.

Only a fixed number of harmless errors are recorded. It is a circular list, so if more than the current maximum is encountered older harmless error messages are lost.

The caller passes in a pointer to an array of pointer-to-char as the argument `errmsg_ptrs_array`. The caller must provide this array, `libdwarf` does not provide it. The caller need not initialize the array elements.

The caller passes in the number of elements of the array of pointer-to-char thru `count`. Since the

If there are no unreported harmless errors the function returns `DW_DLV_NO_ENTRY` and the function arguments are ignored. Otherwise the function returns `DW_DLV_OK` and uses the arguments.

`libdwarf` assigns error strings to the `errmsg_ptrs_array`. The `MINIMUM(count-1, number of messages recorded)` pointers are assigned to the array. The array is terminated with a `NULL` pointer. (That is, one array entry is reserved for a `NULL` pointer). So if `count` is 5 up to 4 strings may be returned through the array, and one array entry is set to `NULL`.

Because the list is circular and messages may have been dropped the function also returns the actual error count of harmless errors encountered through `newerr_count` (unless the argument is `NULL`, in which case it is ignored).

Each call to this function resets the circular error buffer and the error count. So think of this call as reporting harmless errors since the last call to it.

The pointers returned through `errmsg_ptrs_array` are only valid till the next call to `libdwarf`. Do not save the pointers, they become invalid. Copy the strings if you wish to save them.

Calling this function neither allocates any space in memory nor frees any space in memory.

#### **5.53.4 dwarf\_insert\_harmless\_error()**

```
void dwarf_insert_harmless_error(Dwarf_Debug dbg,
    char * newerror);
```

This function is used to test `dwarf_get_harmless_error_list`. It simply adds a harmless error string. There is little reason client code should use this function. It exists so that the harmless error functions can be easily tested for correctness and leaks.

#### **5.53.5 dwarf\_set\_harmless\_error\_list\_size()**

```
unsigned dwarf_set_harmless_error_list_size(Dwarf_Debug dbg,
    unsigned maxcount)
```

`dwarf_set_harmless_error_list_size` returns the number of harmless error strings the library is currently set to hold. If `maxcount` is non-zero the library changes the maximum it will record to be `maxcount`.

It is extremely unwise to make `maxcount` large because `libdwarf` allocates space for `maxcount` strings immediately.

The set of errors enumerated in Figure 3 below were defined in Dwarf 1. These errors are not used by the `libdwarf` implementation for Dwarf 2 or later.



SYMBOLIC NAME	DESCRIPTION
DW_DLE_NE	No error (0)
DW_DLE_VMM	Version of DWARF information newer than libdwarf
DW_DLE_MAP	Memory map failure
DW_DLE_LEE	Propagation of libelf error
DW_DLE_NDS	No debug section
DW_DLE_NLS	No line section
DW_DLE_ID	Requested information not associated with descriptor
DW_DLE_IOF	I/O failure
DW_DLE_MAF	Memory allocation failure
DW_DLE_IA	Invalid argument
DW_DLE_MDE	Mangled debugging entry
DW_DLE_MLE	Mangled line number entry
DW_DLE_FNO	File descriptor does not refer to an open file
DW_DLE_FNR	File is not a regular file
DW_DLE_FWA	File is opened with wrong access
DW_DLE_NOB	File is not an object file
DW_DLE_MOF	Mangled object file header
DW_DLE_EOLL	End of location list entries
DW_DLE_NOLL	No location list section
DW_DLE_BADOFF	Invalid offset
DW_DLE_EOS	End of section
DW_DLE_ATRUNC	Abbreviations section appears truncated
DW_DLE_BADBITC	Address size passed to dwarf bad

**Figure 6.** Dwarf Error Codes

The set of errors returned by `Libdwarf` functions is listed below. Some of the errors are SGI specific.

SYMBOLIC NAME	DESCRIPTION
DW_DLE_DBG_ALLOC	Could not allocate Dwarf_Debug struct
DW_DLE_FSTAT_ERROR	Error in fstat()-ing object
DW_DLE_FSTAT_MODE_ERROR	Error in mode of object file
DW_DLE_INIT_ACCESS_WRONG	Incorrect access to dwarf_init()
DW_DLE_ELF_BEGIN_ERROR	Error in elf_begin() on object
DW_DLE_ELF_GETEHDR_ERROR	Error in elf_getehdr() on object
DW_DLE_ELF_GETSHDR_ERROR	Error in elf_getshdr() on object
DW_DLE_ELF_STRPTR_ERROR	Error in elf_strptr() on object
DW_DLE_DEBUG_INFO_DUPLICATE	Multiple .debug_info sections
DW_DLE_DEBUG_INFO_NULL	No data in .debug_info section
DW_DLE_DEBUG_ABBREV_DUPLICATE	Multiple .debug_abbrev sections
DW_DLE_DEBUG_ABBREV_NULL	No data in .debug_abbrev section
DW_DLE_DEBUG_ARANGES_DUPLICATE	Multiple .debug_arange sections
DW_DLE_DEBUG_ARANGES_NULL	No data in .debug_arange section
DW_DLE_DEBUG_LINE_DUPLICATE	Multiple .debug_line sections
DW_DLE_DEBUG_LINE_NULL	No data in .debug_line section
DW_DLE_DEBUG_LOC_DUPLICATE	Multiple .debug_loc sections
DW_DLE_DEBUG_LOC_NULL	No data in .debug_loc section
DW_DLE_DEBUG_MACINFO_DUPLICATE	Multiple .debug_macinfo sections
DW_DLE_DEBUG_MACINFO_NULL	No data in .debug_macinfo section
DW_DLE_DEBUG_PUBNAMES_DUPLICATE	Multiple .debug_pubnames sections
DW_DLE_DEBUG_PUBNAMES_NULL	No data in .debug_pubnames section
DW_DLE_DEBUG_STR_DUPLICATE	Multiple .debug_str sections
DW_DLE_DEBUG_STR_NULL	No data in .debug_str section
DW_DLE_CU_LENGTH_ERROR	Length of compilation-unit bad
DW_DLE_VERSION_STAMP_ERROR	Incorrect Version Stamp
DW_DLE_ABBREV_OFFSET_ERROR	Offset in .debug_abbrev bad
DW_DLE_ADDRESS_SIZE_ERROR	Size of addresses in target bad
DW_DLE_DEBUG_INFO_PTR_NULL	Pointer into .debug_info in DIE null
DW_DLE_DIE_NULL	Null Dwarf_Die
DW_DLE_STRING_OFFSET_BAD	Offset in .debug_str bad
DW_DLE_DEBUG_LINE_LENGTH_BAD	Length of .debug_line segment bad
DW_DLE_LINE_PROLOG_LENGTH_BAD	Length of .debug_line prolog bad
DW_DLE_LINE_NUM_OPERANDS_BAD	Number of operands to line instr bad
DW_DLE_LINE_SET_ADDR_ERROR	Error in DW_LNE_set_address instruction

**Figure 7.** Dwarf 2 Error Codes (continued below)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_LINE_EXT_OPCODE_BAD	Error in DW_EXTENDED_OPCODE instruction
DW_DLE_DWARF_LINE_NULL	Null Dwarf_line argument
DW_DLE_INCL_DIR_NUM_BAD	Error in included directory for given line
DW_DLE_LINE_FILE_NUM_BAD	File number in .debug_line bad
DW_DLE_ALLOC_FAIL	Failed to allocate required structs
DW_DLE_DBG_NULL	Null Dwarf_Debug argument
DW_DLE_DEBUG_FRAME_LENGTH_BAD	Error in length of frame
DW_DLE_FRAME_VERSION_BAD	Bad version stamp for frame
DW_DLE_CIE_RET_ADDR_REG_ERROR	Bad register specified for return address
DW_DLE_FDE_NULL	Null Dwarf_Fde argument
DW_DLE_FDE_DBG_NULL	No Dwarf_Debug associated with FDE
DW_DLE_CIE_NULL	Null Dwarf_Cie argument
DW_DLE_CIE_DBG_NULL	No Dwarf_Debug associated with CIE
DW_DLE_FRAME_TABLE_COL_BAD	Bad column in frame table specified
DW_DLE_PC_NOT_IN_FDE_RANGE	PC requested not in address range of FDE
DW_DLE_CIE_INSTR_EXEC_ERROR	Error in executing instructions in CIE
DW_DLE_FRAME_INSTR_EXEC_ERROR	Error in executing instructions in FDE
DW_DLE_FDE_PTR_NULL	Null Pointer to Dwarf_Fde specified
DW_DLE_RET_OP_LIST_NULL	No location to store pointer to Dwarf_Frame_Op
DW_DLE_LINE_CONTEXT_NULL	Dwarf_Line has no context
DW_DLE_DBG_NO_CU_CONTEXT	dbg has no CU context for dwarf_siblingof()
DW_DLE_DIE_NO_CU_CONTEXT	Dwarf_Die has no CU context
DW_DLE_FIRST_DIE_NOT_CU	First DIE in CU not DW_TAG_compilation_unit
DW_DLE_NEXT_DIE_PTR_NULL	Error in moving to next DIE in .debug_info
DW_DLE_DEBUG_FRAME_DUPLICATE	Multiple .debug_frame sections
DW_DLE_DEBUG_FRAME_NULL	No data in .debug_frame section
DW_DLE_ABBREV_DECODE_ERROR	Error in decoding abbreviation
DW_DLE_DWARF_ABBREV_NULL	Null Dwarf_Abbrev specified
DW_DLE_ATTR_NULL	Null Dwarf_Attribute specified
DW_DLE_DIE_BAD	DIE bad
DW_DLE_DIE_ABBREV_BAD	No abbreviation found for code in DIE
DW_DLE_ATTR_FORM_BAD	Inappropriate attribute form for attribute
DW_DLE_ATTR_NO_CU_CONTEXT	No CU context for Dwarf_Attribute struct
DW_DLE_ATTR_FORM_SIZE_BAD	Size of block in attribute value bad
DW_DLE_ATTR_DBG_NULL	No Dwarf_Debug for Dwarf_Attribute struct
DW_DLE_BAD_REF_FORM	Inappropriate form for reference attribute
DW_DLE_ATTR_FORM_OFFSET_BAD	Offset reference attribute outside current CU
DW_DLE_LINE_OFFSET_BAD	Offset of lines for current CU outside .debug_line
DW_DLE_DEBUG_STR_OFFSET_BAD	Offset into .debug_str past its end
DW_DLE_STRING_PTR_NULL	Pointer to pointer into .debug_str NULL
DW_DLE_PUBNAMES_VERSION_ERROR	Version stamp of pubnames incorrect
DW_DLE_PUBNAMES_LENGTH_BAD	Read pubnames past end of .debug_pubnames
DW_DLE_GLOBAL_NULL	Null Dwarf_Global specified
DW_DLE_GLOBAL_CONTEXT_NULL	No context for Dwarf_Global given
DW_DLE_DIR_INDEX_BAD	Error in directory index read

**Figure 8.** Dwarf 2 Error Codes (continued below)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_LOC_EXPR_BAD	Bad operator read for location expression
DW_DLE_DIE_LOC_EXPR_BAD	Expected block value for attribute not found
DW_DLE_OFFSET_BAD	Offset for next compilation-unit in .debug_info bad
DW_DLE_MAKE_CU_CONTEXT_FAIL	Could not make CU context
DW_DLE_ARANGE_OFFSET_BAD	Offset into .debug_info in .debug_aranges bad
DW_DLE_SEGMENT_SIZE_BAD	Segment size will be 0 for MIPS processors and should always be < 8.
DW_DLE_ARANGE_LENGTH_BAD	Length of arange section in .debug_arange bad
DW_DLE_ARANGE_DECODE_ERROR	Aranges do not end at end of .debug_aranges
DW_DLE_ARANGES_NULL	NULL pointer to Dwarf_Arange specified
DW_DLE_ARANGE_NULL	NULL Dwarf_Arange specified
DW_DLE_NO_FILE_NAME	No file name for Dwarf_Line struct
DW_DLE_NO_COMP_DIR	No Compilation directory for compilation-unit
DW_DLE_CU_ADDRESS_SIZE_BAD	CU header address size not match Elf class
DW_DLE_ELF_GETIDENT_ERROR	Error in elf_getident() on object
DW_DLE_NO_AT_MIPS_FDE	DIE does not have DW_AT_MIPS_fde attribute
DW_DLE_NO_CIE_FOR_FDE	No CIE specified for FDE
DW_DLE_DIE_ABBREVS_LIST_NULL	No abbreviation for the code in DIE found
DW_DLE_DEBUG_FUNCNAMES_DUPLICATE	Multiple .debug_funcnames sections
DW_DLE_DEBUG_FUNCNAMES_NULL	No data in .debug_funcnames section
DW_DLE_DEBUG_FUNCNAMES_VERSION_ERROR	Version stamp in .debug_funcnames bad
DW_DLE_DEBUG_FUNCNAMES_LENGTH_BAD	Length error in reading .debug_funcnames
DW_DLE_FUNC_NULL	NULL Dwarf_Func specified
DW_DLE_FUNC_CONTEXT_NULL	No context for Dwarf_Func struct
DW_DLE_DEBUG_TYPENAMES_DUPLICATE	Multiple .debug_typenames sections
DW_DLE_DEBUG_TYPENAMES_NULL	No data in .debug_typenames section
DW_DLE_DEBUG_TYPENAMES_VERSION_ERROR	Version stamp in .debug_typenames bad
DW_DLE_DEBUG_TYPENAMES_LENGTH_BAD	Length error in reading .debug_typenames
DW_DLE_TYPE_NULL	NULL Dwarf_Type specified
DW_DLE_TYPE_CONTEXT_NULL	No context for Dwarf_Type given
DW_DLE_DEBUG_VARNAMES_DUPLICATE	Multiple .debug_varnames sections
DW_DLE_DEBUG_VARNAMES_NULL	No data in .debug_varnames section
DW_DLE_DEBUG_VARNAMES_VERSION_ERROR	Version stamp in .debug_varnames bad
DW_DLE_DEBUG_VARNAMES_LENGTH_BAD	Length error in reading .debug_varnames

**Figure 9.** Dwarf 2 Error Codes (continued below)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_VAR_NULL	NULL Dwarf_Var specified
DW_DLE_VAR_CONTEXT_NULL	No context for Dwarf_Var given
DW_DLE_DEBUG_WEAKNAMES_DUPLICATE	Multiple .debug_weaknames section
DW_DLE_DEBUG_WEAKNAMES_NULL	No data in .debug_varnames section
DW_DLE_DEBUG_WEAKNAMES_VERSION_ERROR	Version stamp in .debug_varnames bad
DW_DLE_DEBUG_WEAKNAMES_LENGTH_BAD	Length error in reading .debug_weaknames
DW_DLE_WEAK_NULL	NULL Dwarf_Weak specified
DW_DLE_WEAK_CONTEXT_NULL	No context for Dwarf_Weak given

**Figure 10.** Dwarf 2 Error Codes

This list of errors is not complete; additional errors have been added. Some of the above errors may be unused. Errors may not have the same meaning in different releases. Since most error codes are returned from only one place (or a very small number of places) in the source it is normally very useful to simply search the *libdwarf* source to find out where a particular error code is generated.

#### 5.53.6 dwarf\_seterrhand()

```
Dwarf_Handler dwarf_seterrhand(
    Dwarf_Debug dbg,
    Dwarf_Handler errhand)
```

The function `dwarf_seterrhand()` replaces the error handler (see `dwarf_init()`) with `errhand`. The old error handler is returned. This function is currently unimplemented.

#### 5.53.7 dwarf\_seterrarg()

```
Dwarf_Ptr dwarf_seterrarg(
    Dwarf_Debug dbg,
    Dwarf_Ptr errarg)
```

The function `dwarf_seterrarg()` replaces the pointer to the error handler communication area (see `dwarf_init()`) with `errarg`. A pointer to the old area is returned. This function is currently unimplemented.

#### 5.53.8 dwarf\_dealloc()

```
void dwarf_dealloc(
    Dwarf_Debug dbg,
    void* space,
    Dwarf_Unsigned type)
```

The function `dwarf_dealloc` frees the dynamic storage pointed to by `space`, and allocated to the given `Dwarf_Debug`. The argument `type` is an integer code that specifies the allocation type of the region pointed to by the `space`. Refer to section 4 for details on *libdwarf* memory management.

#### 5.53.9 dwarf\_encode\_leb128()

```
int dwarf_encode_leb128(Dwarf_Unsigned val,  
    int * nbytes,  
    char * space,  
    int splen);
```

The function `dwarf_encode_leb128` encodes the value `val` in the caller-provided buffer that `space` points to. The caller-provided buffer must be at least `splen` bytes long.

The function returns `DW_DLV_OK` if the encoding succeeds. If `splen` is too small to encode the value, `DW_DLV_ERROR` will be returned.

If the call succeeds, the number of bytes of `space` that are used in the encoding are returned through the pointer `nbytes`

#### **5.53.10 dwarf\_encode\_signed\_leb128()**

```
int dwarf_encode_signed_leb128(Dwarf_Signed val,  
    int * nbytes,  
    char * space,  
    int splen);
```

The function `dwarf_encode_signed_leb128` is the same as `dwarf_encode_leb128` except that the argument `val` is signed.



## CONTENTS

1. INTRODUCTION .....	1
1.1 Copyright .....	1
1.2 Purpose and Scope .....	1
1.3 Document History .....	1
1.4 Definitions .....	2
1.5 Overview .....	2
1.6 Items Changed .....	3
1.7 Items Removed .....	4
1.8 Revision History .....	4
2. Types Definitions .....	4
2.1 General Description .....	4
2.2 Scalar Types .....	5
2.3 Aggregate Types .....	5
2.3.1 Location Record .....	5
2.3.2 Location Description .....	6
2.3.3 Data Block .....	7
2.3.4 Frame Operation Codes: DWARF 2 .....	7
2.3.5 Frame Regtable: DWARF 2 .....	8
2.3.6 Frame Operation Codes: DWARF 3 (and DWARF2) .....	8
2.3.7 Frame Regtable: DWARF 3 .....	9
2.3.8 Macro Details Record .....	11
2.4 Opaque Types .....	11
3. Error Handling .....	13
3.1 Returned values in the functional interface .....	14
4. Memory Management .....	15
4.1 Read-only Properties .....	15
4.2 Storage Deallocation .....	15
5. Functional Interface .....	17
5.1 Initialization Operations .....	17
5.1.1 dwarf_init() .....	17
5.1.2 dwarf_elf_init() .....	18
5.1.3 dwarf_get_elf() .....	18
5.1.4 dwarf_finish() .....	19
5.1.5 dwarf_set_stringcheck() .....	19
5.1.6 dwarf_set_reloc_application() .....	19
5.1.7 dwarf_record_cmdline_options() .....	20
5.2 Section size operations .....	20
5.2.1 dwarf_get_section_max_offsets_b() .....	20
5.2.2 dwarf_get_section_max_offsets() .....	20
5.3 Printf Callbacks .....	21
5.3.1 dwarf_register_printf_callback .....	21
5.3.2 Dwarf_Printf_Callback_Info_s .....	21



5.3.3	dwarf_printf_callback_function_type .....	22
5.3.4	Example of printf callback use in a C++ application using libdwarf .....	22
5.4	Debugging Information Entry Delivery Operations .....	22
5.4.1	dwarf_next_cu_header_c() .....	22
5.4.2	dwarf_next_cu_header_b() .....	24
5.4.3	dwarf_next_cu_header() .....	24
5.4.4	dwarf_siblingof_b() .....	24
5.4.5	dwarf_siblingof() .....	25
5.4.6	dwarf_child() .....	25
5.4.7	dwarf_offdie_b() .....	26
5.4.8	dwarf_offdie() .....	26
5.4.9	dwarf_validate_die_sibling() .....	26
5.5	Debugging Information Entry Query Operations .....	27
5.5.1	dwarf_get_die_infotypes_flag() .....	27
5.5.2	dwarf_tag() .....	27
5.5.3	dwarf_dieoffset() .....	28
5.5.4	dwarf_die_CU_offset() .....	28
5.5.5	dwarf_die_offsets() .....	28
5.5.6	dwarf_ptr_CU_offset() .....	28
5.5.7	dwarf_CU_dieoffset_given_die() .....	28
5.5.8	dwarf_die_CU_offset_range() .....	29
5.5.9	dwarf_diename() .....	29
5.5.10	dwarf_die_abbrev_code() .....	30
5.5.11	dwarf_die_abbrev_children_flag() .....	30
5.5.12	dwarf_get_version_of_die() .....	30
5.5.13	dwarf_attrlist() .....	30
5.5.14	dwarf_hasattr() .....	31
5.5.15	dwarf_attr() .....	31
5.5.16	dwarf_lowpc() .....	31
5.5.17	dwarf_highpc_b() .....	32
5.5.18	dwarf_highpc() .....	32
5.5.19	dwarf_bytesize() .....	32
5.5.20	dwarf_bitsize() .....	33
5.5.21	dwarf_bitoffset() .....	33
5.5.22	dwarf_srclang() .....	33
5.5.23	dwarf_arrayorder() .....	33
5.6	Attribute Queries .....	33
5.6.1	dwarf_hasform() .....	34
5.6.2	dwarf_whatform() .....	34
5.6.3	dwarf_whatform_direct() .....	34
5.6.4	dwarf_whatattr() .....	34
5.6.5	dwarf_formref() .....	35
5.6.6	dwarf_global_formref() .....	35
5.6.7	dwarf_convert_to_global_offset() .....	35
5.6.8	dwarf_formaddr() .....	36
5.6.9	dwarf_formflag() .....	36
5.6.10	dwarf_formudata() .....	36
5.6.11	dwarf_formsdata() .....	37

5.6.12	dwarf_formblock()	37
5.6.13	dwarf_formstring()	37
5.6.14	dwarf_formsig8()	37
5.6.15	dwarf_formsig8()	38
5.6.16	dwarf_get_form_class()	38
5.6.17	dwarf_loclist_n()	38
5.6.18	dwarf_loclist()	39
5.6.19	dwarf_loclist_from_expr()	40
5.6.20	dwarf_loclist_from_expr_b()	41
5.6.21	dwarf_loclist_from_expr_a()	42
5.7	Line Number Operations	42
5.7.1	Get A Set of Lines	42
5.7.1.1	dwarf_srclines()	42
5.7.2	Get the set of Source File Names	43
5.7.3	Get information about a Single Table Line	44
5.7.3.1	dwarf_linebeginstatement()	44
5.7.3.2	dwarf_lineendsequence()	44
5.7.3.3	dwarf_lineno()	44
5.7.3.4	dwarf_line_srcfileno()	45
5.7.3.5	dwarf_lineaddr()	45
5.7.3.6	dwarf_lineoff()	45
5.7.3.7	dwarf_linesrc()	45
5.7.3.8	dwarf_lineblock()	46
5.7.3.9	dwarf_is_addr_set()	46
5.7.3.10	dwarf_prologue_end_etc()	46
5.8	Global Name Space Operations	47
5.9	Global Name Space Operations	47
5.9.1	Debugger Interface Operations	47
5.9.1.1	dwarf_get_globals()	47
5.9.1.2	dwarf_globname()	48
5.9.1.3	dwarf_global_die_offset()	48
5.9.1.4	dwarf_global_cu_offset()	48
5.9.1.5	dwarf_get_cu_die_offset_given_cu_header_offset()	49
5.9.1.6	dwarf_get_cu_die_offset_given_cu_header_offset()	49
5.9.1.7	dwarf_global_name_offsets()	49
5.10	DWARF3 Type Names Operations	50
5.10.1	Debugger Interface Operations	50
5.10.1.1	dwarf_get_pubtypes()	50
5.10.1.2	dwarf_pubtypename()	51
5.10.1.3	dwarf_pubtype_die_offset()	51
5.10.1.4	dwarf_pubtype_cu_offset()	51
5.10.1.5	dwarf_pubtype_name_offsets()	51
5.11	User Defined Static Variable Names Operations	52
5.12	Weak Name Space Operations	52
5.12.1	Debugger Interface Operations	52
5.12.1.1	dwarf_get_weakes()	52
5.12.1.2	dwarf_weakname()	53
5.12.1.3	dwarf_weak_cu_offset()	53

5.12.1.4	dwarf_weak_name_offsets()	54
5.13	Static Function Names Operations	54
5.13.1	Debugger Interface Operations	54
5.13.1.1	dwarf_get_funcs()	54
5.13.1.2	dwarf_funcname()	55
5.13.1.3	dwarf_func_die_offset()	55
5.13.1.4	dwarf_func_cu_offset()	56
5.13.1.5	dwarf_func_name_offsets()	56
5.14	User Defined Type Names Operations	56
5.14.1	Debugger Interface Operations	56
5.14.1.1	dwarf_get_types()	57
5.14.1.2	dwarf_typename()	58
5.14.1.3	dwarf_type_die_offset()	58
5.14.1.4	dwarf_type_cu_offset()	58
5.14.1.5	dwarf_type_name_offsets()	58
5.15	User Defined Static Variable Names Operations	59
5.15.1	Debugger Interface Operations	59
5.15.1.1	dwarf_get_vars()	59
5.15.1.2	dwarf_varname()	60
5.15.1.3	dwarf_var_die_offset()	60
5.15.1.4	dwarf_var_cu_offset()	61
5.15.1.5	dwarf_var_name_offsets()	61
5.16	Macro Information Operations	61
5.16.1	General Macro Operations	61
5.16.1.1	dwarf_find_macro_value_start()	61
5.16.2	Debugger Interface Macro Operations	61
5.16.3	Low Level Macro Information Operations	62
5.16.3.1	dwarf_get_macro_details()	62
5.17	Low Level Frame Operations	62
5.17.0.1	dwarf_get_fde_list()	65
5.17.0.2	dwarf_get_fde_list_eh()	66
5.17.0.3	dwarf_get_cie_of_fde()	67
5.17.0.4	dwarf_get_fde_for_die()	67
5.17.0.5	dwarf_get_fde_range()	68
5.17.0.6	dwarf_get_cie_info()	68
5.17.0.7	dwarf_get_cie_index()	69
5.17.0.8	dwarf_get_fde_instr_bytes()	69
5.17.0.9	dwarf_get_fde_info_for_reg()	69
5.17.0.10	dwarf_get_fde_info_for_all_regs()	70
5.17.0.11	dwarf_set_frame_rule_table_size()	70
5.17.0.12	dwarf_set_frame_rule_initial_value()	71
5.17.0.13	dwarf_set_frame_cfa_value()	71
5.17.0.14	dwarf_set_frame_same_value()	71
5.17.0.15	dwarf_set_frame_undefined_value()	71
5.17.0.16	dwarf_set_default_address_size()	72
5.17.0.17	dwarf_get_fde_info_for_reg3()	72
5.17.0.18	dwarf_get_fde_info_for_cfa_reg3()	73
5.17.0.19	dwarf_get_fde_info_for_all_regs3()	74

5.17.0.20 dwarf_get_fde_n()	74
5.17.0.21 dwarf_get_fde_at_pc()	75
5.17.0.22 dwarf_expand_frame_instructions()	75
5.17.0.23 dwarf_get_fde_exception_info()	76
5.18 Location Expression Evaluation	76
5.18.1 Location List Internal-level Interface	76
5.18.1.1 dwarf_get_loclist_entry()	76
5.19 Abbreviations access	77
5.19.1 dwarf_get_abbrev()	77
5.19.2 dwarf_get_abbrev_tag()	78
5.19.3 dwarf_get_abbrev_code()	78
5.19.4 dwarf_get_abbrev_children_flag()	78
5.19.5 dwarf_get_abbrev_entry()	78
5.20 String Section Operations	79
5.20.1 dwarf_get_str()	79
5.21 Address Range Operations	79
5.21.1 dwarf_get_aranges()	79
5.21.2 dwarf_get_arange()	80
5.21.3 dwarf_get_cu_die_offset()	80
5.21.4 dwarf_get_arange_cu_header_offset()	80
5.21.5 dwarf_get_arange_info()	81
5.22 General Low Level Operations	81
5.22.1 dwarf_get_address_size()	81
5.22.2 dwarf_get_die_address_size()	81
5.23 Ranges Operations (.debug_ranges)	82
5.24 Ranges Operations (.debug_ranges)	82
5.24.1 dwarf_get_ranges()	82
5.24.2 dwarf_get_ranges_a()	82
5.24.3 dwarf_ranges_dealloc()	83
5.25 TAG ATTR etc names as strings	83
5.26 dwarf_get_ACCESS_name()	84
5.27 dwarf_get_AT_name()	84
5.28 dwarf_get_ATE_name()	84
5.29 dwarf_get_ADDR_name()	84
5.30 dwarf_get_ATCF_name()	84
5.31 dwarf_get_CHILDREN_name()	84
5.32 dwarf_get_children_name()	84
5.33 dwarf_get_CC_name()	85
5.34 dwarf_get_CFA_name()	85
5.35 dwarf_get_DS_name()	85
5.36 dwarf_get_DSC_name()	85
5.37 dwarf_get_EH_name()	85
5.38 dwarf_get_END_name()	85
5.39 dwarf_get_FORM_name()	85
5.40 dwarf_get_FRAME_name()	85
5.41 dwarf_get_ID_name()	85
5.42 dwarf_get_INL_name()	85
5.43 dwarf_get_LANG_name()	85

5.44 dwarf_get_LNE_name()	85
5.45 dwarf_get_LNS_name()	85
5.46 dwarf_get_MACINFO_name()	85
5.47 dwarf_get_OP_name()	85
5.48 dwarf_get_ORD_name()	86
5.49 dwarf_get_TAG_name()	86
5.50 dwarf_get_VIRTUALITY_name()	86
5.51 dwarf_get_VIS_name()	86
5.52 Section Operations	86
5.52.1 dwarf_get_section_count()	86
5.52.2 dwarf_get_section_info_by_name()	86
5.52.3 dwarf_get_section_info_by_index()	86
5.53 Utility Operations	87
5.53.1 dwarf_errno()	87
5.53.2 dwarf_errmsg()	87
5.53.3 dwarf_get_harmless_error_list()	87
5.53.4 dwarf_insert_harmless_error()	88
5.53.5 dwarf_set_harmless_error_list_size()	88
5.53.6 dwarf_seterrhand()	93
5.53.7 dwarf_seterrarg()	93
5.53.8 dwarf_dealloc()	93
5.53.9 dwarf_encode_leb128()	93
5.53.10 dwarf_encode_signed_leb128()	94

## LIST OF FIGURES

Figure 1. Scalar Types .....	5
Figure 2. Error Indications .....	14
Figure 3. Allocation/Deallocation Identifiers .....	17
Figure 4. Frame Information Rule Assignments MIPS .....	64
Figure 5. Frame Information Special Values any architecture .....	64
Figure 6. Dwarf Error Codes .....	89
Figure 7. Dwarf 2 Error Codes (continued below) .....	90
Figure 8. Dwarf 2 Error Codes (continued below) .....	91
Figure 9. Dwarf 2 Error Codes (continued below) .....	92
Figure 10. Dwarf 2 Error Codes .....	93

# **A Consumer Library Interface to DWARF**

*David Anderson*

## *ABSTRACT*

This document describes an interface to a library of functions to access DWARF debugging information entries and DWARF line number information (and other DWARF2/3 information). It does not make recommendations as to how the functions described in this document should be implemented nor does it suggest possible optimizations.

The document is oriented to reading DWARF version 2 and version 3. There are certain sections which are SGI-specific (those are clearly identified in the document).

rev 2.16, January 30, 2014

---

0. UNIX is a registered trademark of UNIX System Laboratories, Inc. in the United States and other countries.